

Elastic Volume Service

FAQs

Issue	01
Date	2025-08-04



Copyright © Huawei Technologies Co., Ltd. 2025. All rights reserved.

No part of this document may be reproduced or transmitted in any form or by any means without prior written consent of Huawei Technologies Co., Ltd.

Trademarks and Permissions



HUAWEI and other Huawei trademarks are trademarks of Huawei Technologies Co., Ltd.

All other trademarks and trade names mentioned in this document are the property of their respective holders.

Notice

The purchased products, services and features are stipulated by the contract made between Huawei and the customer. All or part of the products, services and features described in this document may not be within the purchase scope or the usage scope. Unless otherwise specified in the contract, all statements, information, and recommendations in this document are provided "AS IS" without warranties, guarantees or representations of any kind, either express or implied.

The information in this document is subject to change without notice. Every effort has been made in the preparation of this document to ensure accuracy of the contents, but all statements, information, and recommendations in this document do not constitute a warranty of any kind, express or implied.

Security Declaration

Vulnerability

Huawei's regulations on product vulnerability management are subject to the *Vul. Response Process*. For details about this process, visit the following web page:

<https://www.huawei.com/en/psirt/vul-response-process>

For vulnerability information, enterprise customers can visit the following web page:

<https://securitybulletin.huawei.com/enterprise/en/security-advisory>

Contents

1 Summary.....	1
2 General.....	4
2.1 How Do I Start Using a Newly Purchased Disk?.....	4
2.2 Can EVS Disks Be Used Directly for Storage?.....	4
2.3 Can EVS Disks Be Used Alone?.....	4
2.4 How Can I View My Disk Details?.....	4
2.5 How Do I Change the Name of My Disk?.....	5
2.6 Can I Change the AZ of My Disk?.....	5
2.7 Can I Change the Disk Type, Device Type, or Sharing Attribute of My Disk?.....	6
2.8 What Should I Do If an Error Occurs on My EVS Disk?.....	7
2.9 How Can I Obtain ECS NIC Information?.....	8
2.10 Why Do Some of My EVS Disks Not Have WWN Information?.....	8
2.11 How Can I Migrate Data from an EVS Disk?.....	9
2.12 What Are the Differences Between System Disks and Data Disks?.....	9
2.13 Will I Lose My Disk Data If I Reinstall ECS OS, Change the OS, or Change the ECS Specifications?....	10
2.14 How Can I Export the Original Data After I Changed My Server OS from Windows to CentOS?.....	11
2.15 What Are the Differences Between MBR and GPT Partition Styles?.....	11
2.16 What Does the "reserveVolume" Trace Mean in CTS?.....	13
2.17 How Can I Download My EVS Disk Data to a Local PC?.....	13
2.18 How Can I Upload Files to My EVS Disk?.....	13
3 Billing.....	14
3.1 How Can I Stop Being Billed for My Disk?.....	14
3.2 Will I Be Billed If I Have Purchased an EVS Disk But Not Used It?.....	14
3.3 How Can I Delete or Unsubscribe from a Yearly/Monthly Disk?.....	14
3.4 Can I Recover My Disk Data If the Disk Is Unsubscribed from, Deleted by Mistake, or Released After the Retention Period Ends?.....	15
3.5 Will My EVS Disk Be Unsubscribed from or Deleted When I Unsubscribe from or Delete Its Server?...	15
3.6 Will I Be Billed for the Disks in the Recycle Bin?.....	16
4 Attachment.....	17
4.1 Why Can't I View the Attached Data Disk on the Server?.....	17
4.2 Why Can't I Attach My Disk to a Server?.....	20
4.3 Can I Attach a Disk to Multiple Servers?.....	22

4.4 Can I Attach a Disk to a Server in a Different AZ?.....	23
4.5 How Can I Add a Data Disk to an Existing Server?.....	23
4.6 Can I Attach a Yearly/Monthly Disk to Another Server?.....	24
4.7 Can I Attach Different Types of Disks to the Same Server?.....	24
4.8 Can I Switch Between System Disks and Data Disks?.....	24
4.9 What Should I Do If a Linux EVS Disk Is Attached to a Windows Server?.....	25
4.10 Can I Attach an EVS Disk Purchased with a Yearly/Monthly Server to Another Yearly/Monthly Server?.....	25
4.11 Can I Change the Function of a System Disk or Data Disk Purchased Along with a Server?.....	25
4.12 How Do I Obtain My Disk Device Name in the ECS OS Using the Device Identifier Provided on the Console?.....	26
4.13 How Can I View Data on My Disk If Its Yearly/Monthly Server Has Expired?.....	31
5 Capacity Expansion.....	32
5.1 Can I Reduce or Temporarily Expand the Disk Capacity?.....	32
5.2 What Are the Differences Between Expanding Capacity by Expanding an EVS Disk and Creating a New EVS Disk?.....	32
5.3 Will My Disk Data Be Lost After I Expand the Disk Capacity?.....	32
5.4 Can I Use Backups or Snapshots Created Before Capacity Expansion to Restore Data on Expanded Disks?.....	33
5.5 Do I Need to Restart the Server After Expanding the Disk Capacity?.....	33
5.6 Do I Need to Detach an EVS Disk Before Expanding Its Capacity?.....	33
5.7 What Should I Do If My Disk Capacity Exceeds 2 TiB After Expansion?.....	34
5.8 How Can I Allocate Newly Added Space to a New Partition?.....	34
5.9 How Can I Allocate Newly Added Space to an Existing Partition?.....	35
5.10 Why Did My Disk Capacity Remain Unchanged on the Server After a Capacity Expansion?.....	35
5.11 Why Can't I Expand Capacity for My Disk?.....	35
5.12 How Do I Extend the File System of an Unpartitioned Data Disk in Linux?.....	37
5.13 How Do I Extend the Root Partition of a Quickly Provisioned BMS?.....	39
5.14 How Do I Check the Disk Partition Style in Linux?.....	42
6 Detachment.....	46
6.1 If I Detach a Disk, Will I Lose the Data on My Disk?.....	46
6.2 Why Can't I Detach My Disk?.....	47
7 Deletion.....	48
7.1 How Can I Recover Data from a Disk That Was Accidentally Deleted?.....	48
7.2 Why Can't I Delete My Disk?.....	48
8 Capacity.....	50
8.1 What Is the Maximum Capacity Supported for the System and Data Disks?.....	50
8.2 What Should I Do If My Disk Starts to Run Out of Space?.....	50
8.3 How Do I Clean Up My Disk Space on a Windows Server?.....	51
8.4 What Can I Do If the Capacity of My Disk Reaches the Maximum But I Still Need More Space?.....	54
8.5 What Should I Do If I Use fdisk to Initialize a Disk Larger Than 2 TiB and Then the Space in Excess of 2 TiB Cannot Be Displayed?.....	54

8.6 How Can I View the Available Capacity of My Disk?.....	54
8.7 How Can I Monitor My Disk Usages?.....	62
8.8 Can I Transfer the Data Disk Capacity to a System Disk?.....	67
8.9 Why the Space of My New Disk Is Full After I Uploaded Only 500 MB of Files to the Disk?.....	67
9 Snapshot.....	70
9.1 What Are the Typical Causes of a Snapshot Creation Failure?.....	70
9.2 Does EVS Support Automatic Snapshot Creation?.....	70
9.3 Can I Create Snapshots for Multiple Disks at a Time?.....	70
9.4 How Is a Snapshot Created for My Disk?.....	70
9.5 Why Can't I Roll Back My Disk Data from a Snapshot?.....	71
9.6 Can I Roll Back Data from a Snapshot After Reinstalling the OS or Formatting a Disk?.....	71
9.7 How Is the Snapshot Size Calculated?.....	71
9.8 Do Snapshots Take Space on the Disk?.....	71
9.9 Can I Perform Multiple Rollback Operations for a Snapshot?.....	72
9.10 Can I Replicate Snapshots to Other Regions or Accounts?.....	72
9.11 Why Can't I Find My Snapshot?.....	72
9.12 Can I Use a Snapshot to Create a Disk and Roll Back Disk Data at Almost the Same Time?.....	72
10 Performance.....	73
10.1 How Do I Test My Disk Performance?.....	73
10.2 Why Does My Disk Performance Test Using Fio Have Incorrect Results?.....	80
10.3 How Can I Handle a Slowdown in Disk Read/Write Speed or Increased I/Os?.....	82
10.4 How Can I Improve My Disk Performance?.....	83
10.5 Why My Disk's Read IOPS Can't Reach the Theoretical Maximum IOPS When the Disk I/O Usage Is Almost 100%?.....	83
11 Sharing.....	85
11.1 Do I Have to Deploy a Cluster to Use Shared Disks?.....	85
11.2 How Many Servers Can I Attach a Shared Disk to?.....	85
11.3 How Can I Attach a Shared Disk to Multiple Servers?.....	85
11.4 Can a Shared Disk Be Attached to Servers That Belong to Different Accounts?.....	85
11.5 Can I Attach a Shared Disk to Servers Running Different OSs?.....	86
12 Backup.....	87
12.1 Do I Need to Stop the Server Before Performing a Disk Backup?.....	87
12.2 Can I Back Up and Restore My EVS Disk to a Different Region?.....	87
12.3 How Do I Check the Backup Data of My Disk?.....	87

1 Summary

General

- [How Do I Start Using a Newly Purchased Disk?](#)
- [Can EVS Disks Be Used Directly for Storage?](#)
- [Can EVS Disks Be Used Alone?](#)
- [Can I Change the AZ of My Disk?](#)
- [Can I Change the Disk Type, Device Type, or Sharing Attribute of My Disk?](#)
- [What Should I Do If an Error Occurs on My EVS Disk?](#)
- [Why Do Some of My EVS Disks Not Have WWN Information?](#)
- [How Can I Migrate Data from an EVS Disk?](#)
- [What Are the Differences Between System Disks and Data Disks?](#)
- [How Can I Upload Files to My EVS Disk?](#)

Billing

- [Will I Be Billed If I Have Purchased an EVS Disk But Not Used It?](#)
- [How Can I Stop Being Billed for My Disk?](#)
- [How Can I Delete or Unsubscribe from a Yearly/Monthly Disk?](#)
- [Can I Recover My Disk Data If the Disk Is Unsubscribed from, Deleted by Mistake, or Released After the Retention Period Ends?](#)
- [Will My EVS Disk Be Unsubscribed from or Deleted When I Unsubscribe from or Delete Its Server?](#)

Capacity Expansion

- [Can I Reduce or Temporarily Expand the Disk Capacity?](#)
- [What Are the Differences Between Expanding Capacity by Expanding an EVS Disk and Creating a New EVS Disk?](#)
- [Will My Disk Data Be Lost After I Expand the Disk Capacity?](#)
- [Can I Use Backups or Snapshots Created Before Capacity Expansion to Restore Data on Expanded Disks?](#)
- [Do I Need to Restart the Server After Expanding the Disk Capacity?](#)

- [Do I Need to Detach an EVS Disk Before Expanding Its Capacity?](#)
- [What Should I Do If My Disk Capacity Exceeds 2 TiB After Expansion?](#)
- [How Can I Allocate Newly Added Space to a New Partition?](#)
- [How Can I Allocate Newly Added Space to an Existing Partition?](#)
- [Why Did My Disk Capacity Remain Unchanged on the Server After a Capacity Expansion?](#)
- [Why Can't I Expand Capacity for My Disk?](#)
- [How Do I Extend the File System of an Unpartitioned Data Disk in Linux?](#)

Attachment

- [Why Can't I View the Attached Data Disk on the Server?](#)
- [Why Can't I Attach My Disk to a Server?](#)
- [Can I Attach a Disk to Multiple Servers?](#)
- [Can I Attach a Disk to a Server in a Different AZ?](#)
- [How Can I Add a Data Disk to an Existing Server?](#)
- [Can I Attach a Yearly/Monthly Disk to Another Server?](#)
- [Can I Attach Different Types of Disks to the Same Server?](#)
- [Can I Switch Between System Disks and Data Disks?](#)
- [What Should I Do If a Linux EVS Disk Is Attached to a Windows Server?](#)
- [Can I Attach an EVS Disk Purchased with a Yearly/Monthly Server to Another Yearly/Monthly Server?](#)

Detachment

- [If I Detach a Disk, Will I Lose the Data on My Disk?](#)
- [Why Can't I Detach My Disk?](#)

Deletion

- [How Can I Recover Data from a Disk That Was Accidentally Deleted?](#)
- [Why Can't I Delete My Disk?](#)

Capacity

- [What Is the Maximum Capacity Supported for the System and Data Disks?](#)
- [What Should I Do If My Disk Starts to Run Out of Space?](#)
- [What Can I Do If the Capacity of My Disk Reaches the Maximum But I Still Need More Space?](#)
- [What Should I Do If I Use fdisk to Initialize a Disk Larger Than 2 TiB and Then the Space in Excess of 2 TiB Cannot Be Displayed?](#)
- [How Can I View the Available Capacity of My Disk?](#)
- [How Can I Monitor My Disk Usages?](#)
- [Can I Transfer the Data Disk Capacity to a System Disk?](#)

Performance

- [How Do I Test My Disk Performance?](#)
- [Why Does My Disk Performance Test Using Fio Have Incorrect Results?](#)
- [How Can I Handle a Slowdown in Disk Read/Write Speed or Increased I/Os?](#)
- [How Can I Improve My Disk Performance?](#)

Sharing

- [Do I Have to Deploy a Cluster to Use Shared Disks?](#)
- [How Many Servers Can I Attach a Shared Disk to?](#)
- [How Can I Attach a Shared Disk to Multiple Servers?](#)
- [Can I Attach a Shared Disk to Servers Running Different OSs?](#)

Snapshot

- [What Are the Typical Causes of a Snapshot Creation Failure?](#)
- [Does EVS Support Automatic Snapshot Creation?](#)
- [Can I Create Snapshots for Multiple Disks at a Time?](#)
- [How Is a Snapshot Created for My Disk?](#)
- [Why Can't I Roll Back My Disk Data from a Snapshot?](#)
- [Can I Roll Back Data from a Snapshot After Reinstalling the OS or Formatting a Disk?](#)
- [How Is the Snapshot Size Calculated?](#)
- [Do Snapshots Take Space on the Disk?](#)

Backup

- [Do I Need to Stop the Server Before Performing a Disk Backup?](#)
- [Can I Back Up and Restore My EVS Disk to a Different Region?](#)

2 General

2.1 How Do I Start Using a Newly Purchased Disk?

A newly purchased disk must be attached to a server and then initialized in the server OS before you can use it.

For more information, see [Purchasing and Using an EVS Disk](#).

2.2 Can EVS Disks Be Used Directly for Storage?

No.

EVS disks must be attached to cloud servers before use. You cannot use EVS disks alone to store data.

2.3 Can EVS Disks Be Used Alone?

No.

EVS disks must be attached to servers before you can use them.

2.4 How Can I View My Disk Details?

To do so, perform the following operations:

Step 1 Sign in to the console.

Step 2 Choose **Storage > Elastic Volume Service** to go to the EVS console.

Step 3 Locate the row that contains the target disk and view the disk specifications, attributes, and billing mode.

Step 4 (Optional) Click the disk name to view more information, such as the disk backup and snapshot information.

View more information on the **Summary** tab.

----End

2.5 How Do I Change the Name of My Disk?

Scenarios

Disk names are used to identify disks. After a disk is created, you can perform operations in this section to change the disk name if needed.

Procedure

Step 1 Sign in to the [EVS console](#).

Step 2 Choose **Storage > Elastic Volume Service**.

The **Elastic Volume Service** page is displayed.

Step 3 Change the disk name in either of the following ways:

- Perform the following steps to change the disk name in the disk list:
 - a. In the disk list, locate the target disk in the **Name/ID** column and click  to the right of the disk name.
The **Edit Disk Name** dialog box is displayed.
 - b. Enter a new name.
 - c. Click **OK**.
After the change is successful, the new disk name is displayed in the disk list.
- Perform the following steps to change the disk name on the disk details page:
 - a. In the disk list, locate the desired disk and click the disk name.
The disk details page is displayed.
 - b. Click  next to the disk name.
 - c. Enter a new name.
 - d. Click .
After the change is successful, the new disk name is displayed on the disk details page.

----End

2.6 Can I Change the AZ of My Disk?

No.

The AZ of a disk cannot be changed after you have purchased the disk. If you want to change the AZ, unsubscribe or delete the disk and then purchase a new one.

2.7 Can I Change the Disk Type, Device Type, or Sharing Attribute of My Disk?

The following table describes whether the disk type, device type, encryption, and sharing attributes of a disk can be changed.


Table 2-1 EVS disk change description

Attribute	Allow Change	Change Direction
Disk type	Yes (OBT)	For details, see Changing the EVS Disk Type (OBT) .
Sharing	No	- From shared to non-shared - From non-shared to shared
Device type	No	- From SCSI to VBD - From VBD to SCSI
Encryption	No	- From non-encrypted to encrypted - From encrypted to non-encrypted

However, you can:

1. Create a backup for the disk.

Figure 2-1 Create Backup



2. Create a new disk from this backup. During the creation, configure advanced settings (sharing, SCSI, and encryption) based on your service requirements.

Figure 2-2 Create from backup

< Buy Disk

Region

CN North-Beijing4

Regions are geographic areas isolated from each other. Resources are region-specific and cannot be used across regions through internal network connections. For low network latency and quick resource access, select the nearest region.

AZ

AZ1

AZ2 (1)

AZ3

AZ7

No server is available in the current AZ. Select the AZ where your server resides. The AZ cannot be changed after the disk is created.

Attach To Server (Optional)

Select Server

To make sure the disk can be used properly, select a server here.

Billing Mode

Yearly/Monthly

Pay-per-use

Disks are billed based on capacity and duration of use, and fees are paid after use. Select this option if your requirements may change over time.

Data Source (Optional)

Create from

Disk Specifications

Backup

Snapshot

Image

10 GIB

Selected Specifications

10 GIB

Automatic Backup

Do not use

Use existing

Buy new

Cloud Backup and Recovery (CBR) allows you to back up and restore the disk data to any backup point. To use CBR, buy a disk backup vault first. Vaults are containers that store backups.

More

Share

SCSI

Encryption

Tag

2.8 What Should I Do If an Error Occurs on My EVS Disk?

If an error occurs, the disk may show one of the states listed in the following table. Take the measures described in the table to handle the exceptions.

Table 2-2 Solutions for disk errors

Error Status	Handling Suggestion
Error	Delete the disk in the Error state and create another one. - If you select Pay-per-use to create the disk and an error occurs during disk creation, no charges are generated. - If you select Yearly/Monthly to create the disk and an error occurs during disk creation, customer service personnel will help you handle the error. If the issue is urgent, you can contact our customer service personnel directly.
Deletion failed	Contact customer service.
Expansion failed	Our customer service personnel will contact you and help you handle this error. Do not perform any operations on the disk before the customer service personnel contact you. If the issue is urgent, you can contact our customer service personnel directly.

Error Status	Handling Suggestion
Restoration failed	Our customer service personnel will contact you and help you handle this error. Do not perform any operations on the disk before the customer service personnel contact you. If the issue is urgent, you can contact our customer service personnel directly.
Rollback failed	You can roll back the snapshot data to the disk again.

2.9 How Can I Obtain ECS NIC Information?

Scenarios

Obtain the ECS NIC information, such as the ECS IP address.

Procedure

Step 1 Sign in to the console.

Step 2 Choose **Compute > Elastic Cloud Server**.

The ECS console is displayed.

Step 3 In the ECS list, click the target ECS name.

The ECS details page is displayed.

Step 4 Click the **Network Interfaces** tab.

The network interfaces page is displayed.

Step 5 On the **Network Interfaces** tab, click  to view information about an ECS network interface.

Step 6 To view the virtual IP address, click **Manage Virtual IP Address**.

The virtual IP address details page is displayed. You can find the bound virtual IP address based on the ECS network interface information.

----End

2.10 Why Do Some of My EVS Disks Not Have WWN Information?

EVS disks have two device types: VBD and SCSI. WWNs are used as the unique identifiers for SCSI EVS disks, and VBD EVS disks do not have WWNs.

You can view the WWN of a SCSI EVS disk on the console. The details are as follows:

- If the SCSI EVS disk is brand new, you can view the disk WWN on the disk details page.

[Figure 2-3](#) shows the query result.

Figure 2-3 Queried WWN information

WWN: ? 6888603000038430fa17a17502223655

- If the SCSI EVS disk was created before the WWN feature rollout, the disk WWN will fail to be obtained.

[Figure 2-4](#) shows the query result.

Figure 2-4 No WWN information

WWN: ? --

2.11 How Can I Migrate Data from an EVS Disk?

Data migration involves the following scenarios:

- Cross-AZ data migration: Disk data can be migrated from one AZ to another through disk backups. You can create backups for your disks using the CBR service, and then use these backups to create new disks in the target AZ. For details, see [Creating a Cloud Disk Backup](#) and [Creating a Disk from a Cloud Disk Backup](#).
- Cross-region data migration: You can create a data disk image from the data disk in the current region and replicate the image to the other region. Then you can use the data disk image to create data disks in that other region. For details, see [Creating a Data Disk Image from an ECS](#).
- Cross-account data migration: You can create a data disk image from the data disk under one account and then share the image with another account. Then you can use the data disk image under that second account to create data disks. For details, see [Creating a Data Disk Image from an ECS](#).

2.12 What Are the Differences Between System Disks and Data Disks?

- A system disk runs the server OS. It is like drive C in a PC.
When a server is purchased, a system disk is automatically purchased and attached. You cannot purchase a system disk separately. The maximum size of a system disk is 1,024 GiB.
- Data disks store the server data. They are like drive D, drive E, and drive F in a PC.
Data disks can be purchased during or after the server purchase. If you purchase data disks during the server purchase, the system will automatically attach the data disks to the server. If you purchase data disks after the server purchase, you need to manually attach the data disks. The maximum size of a data disk is 32,768 GiB.

If one system disk already meets your business needs, you do not need to purchase data disks. As your business grows, you can purchase data disks when needed.

If the disk paths in your service systems cannot be changed or are difficult to change, you are advised to purchase data disks according to your system planning.

2.13 Will I Lose My Disk Data If I Reinstall ECS OS, Change the OS, or Change the ECS Specifications?

Table 2-3 Impact

Item	OS Reinstallation	OS Change	Specifications Modification
Application scenario	Initialize an ECS. The ECS OS remains unchanged after OS change.	Change the OS of an ECS by changing its image. OS change between Windows and Linux is supported only in the Chinese mainland regions. For details about OS change constraints, see Changing the OS .	Change ECS specifications, such as increasing the number of vCPUs or adding memory, to meet your service requirements.
Billing	OS reinstallation is free of charge. The ECS price remains unchanged.	OS change is free of charge. However, you will be billed based on your new image type after OS change. For details, see Product Price Details .	Modifying ECS specifications is free of charge. However, you will be billed based on the new specifications after modification. For details, see Pricing of a Changed Specification .
IP address	The private IP address, EIP, and MAC address remain unchanged.	The private IP address, EIP, and MAC address remain unchanged.	The private IP address, EIP, and MAC address remain unchanged.
System disk	Reinstalling OS will clear the data in all partitions of the ECS system disk. Back up data before reinstalling the OS.	Changing OS will clear the data in all partitions of the ECS system disk. Back up data before changing the OS.	No impact on system disk.

Item	OS Reinstallation	OS Change	Specifications Modification
Data disk	No impact on data disk.	No impact on data disk.	No impact on data disk.
Backup	Back up data before reinstalling the OS to prevent data loss.	Back up data before changing the OS to prevent data loss.	Create a system disk snapshot before modifying ECS specifications to prevent data loss.

2.14 How Can I Export the Original Data After I Changed My Server OS from Windows to CentOS?

Solution:

1. Install the ntfsprogs software to enable Linux to access the NTFS file system.
yum install ntfsprogs
2. View the data disks previously attached to Windows.
parted -l
3. Mount the data disks.
mount -t ntfs-3g <data-disk-path> <mount-point>

2.15 What Are the Differences Between MBR and GPT Partition Styles?

[Table 2-4](#) lists the common disk partition styles. In Linux, different partition styles require different partitioning tools.

Table 2-4 Disk partition styles

Disk Partition Style	Max. Disk Capacity Supported	Max. Number of Partitions Supported	Linux Partitioning Tool
Master Boot Record (MBR)	2 TiB	• Four primary partitions • Three primary partitions and one extended partition With MBR, you can create several primary partitions and one extended partition. The extended partition must be divided into logical partitions before use. For example, to create six partitions, you can create them in the following two ways: • Three primary partitions and one extended partition, with the extended partition divided into three logical partitions • One primary partition and one extended partition, with the extended partition divided into five logical partitions	You can use either of the following tools: • fdisk • parted
Guid Partition Table (GPT)	18 EiB 1 EiB = 1048576 TiB	Unlimited GPT partitions are not categorized.	parted

NOTICE

The maximum disk size supported by MBR is 2 TiB, and that supported by GPT is 18 EiB. Because an EVS data disk currently supports up to 32 TiB, use GPT if your disk size is greater than 2 TiB.

If you change the partition style after the disk has been used, the data on the disk will be cleared. Therefore, select an appropriate partition style when initializing the disk.

2.16 What Does the "reserveVolume" Trace Mean in CTS?

Before an EVS disk is attached, the system will call the reserveVolume EVS API to check whether the disk can be attached. If it can be attached, the system then changes the disk status to **attaching** to avoid conflicts with other operations.

2.17 How Can I Download My EVS Disk Data to a Local PC?

EVS disk data cannot be directly saved to a local PC. It is recommended that you use a third-party tool, such as FTP, to download the data.

2.18 How Can I Upload Files to My EVS Disk?

EVS disks must be attached to servers before you can use them. For how to upload files, see [How Do I Upload Files to My ECS?](#)

3 Billing

3.1 How Can I Stop Being Billed for My Disk?

- Pay-per-use disk: Just delete the disk. You will not be billed for a disk after it is deleted. For details, see [Unsubscribing from or Deleting an EVS Disk](#).
- Yearly/monthly disk: A yearly/monthly disk cannot be deleted, but you can unsubscribe from it if needed. For details, see [Unsubscribing from or Deleting an EVS Disk](#).

3.2 Will I Be Billed If I Have Purchased an EVS Disk But Not Used It?

Yes, you will be billed by disk capacity after you have purchased the disk. The disk billing is irrelevant to whether the disk is attached, how much disk space is used, or whether the attached server is stopped or not.

If your disks are no longer needed, to stop being billed for their use, take the following actions:

- Pay-per-use disk: Just delete the disk. You will not be billed for a disk after it is deleted. For details, see [Unsubscribing from or Deleting an EVS Disk](#).
- Yearly/monthly disk: A yearly/monthly disk cannot be deleted, but you can unsubscribe from it if needed. For details, see [Unsubscribing from or Deleting an EVS Disk](#).

3.3 How Can I Delete or Unsubscribe from a Yearly/Monthly Disk?

Yearly/Monthly disks cannot be deleted. You can unsubscribe from them if needed. For details, see [Unsubscribing from or Deleting an EVS Disk](#). To learn more about unsubscriptions, see [Unsubscription Overview](#).

- Yearly/Monthly system disks cannot be unsubscribed from separately. They must be unsubscribed from together with their servers.

- Non-shared, yearly/monthly data disks purchased together with or later added to a yearly/monthly server have the same expiration time as the server. They can be unsubscribed from together with the server or separately when their statuses are **In-use**, **Available**, or **Error**.
- Yearly/Monthly data disks purchased on the EVS console have different expiration times as the server. They can be unsubscribed from separately.

3.4 Can I Recover My Disk Data If the Disk Is Unsubscribed from, Deleted by Mistake, or Released After the Retention Period Ends?

You can try the following methods to find your data back.

Method	Operation Instruction
Restoring data by recovering the disk	If you have enabled EVS recycle bin, check whether the deleted disk is in the recycle bin. NOTE EVS disks released after the retention period expires will not be moved to the recycle bin.
Restoring data from a snapshot	If you have created standard snapshots for the disk, create a new disk from a snapshot. For details, see Creating a Disk from a Snapshot
Restoring data from a disk backup	If you have created backups for the disk, create a new disk from a backup. The new disk will contain the backup data after being created. For details, see Creating a Disk from a Cloud Disk Backup .
Restoring data from a server backup	If the disk backup is included in a server backup, create a new server from the server backup. You can choose to restore data to the original disk or a different disk from the server backup. For details, see Restoring from a Cloud Server Backup .

3.5 Will My EVS Disk Be Unsubscribed from or Deleted When I Unsubscribe from or Delete Its Server?

- For pay-per-use disks:
 - If such disks are separately purchased and are attached, the system will prompt you whether to delete them when you delete the server. You can make the decision based on your requirements.
 - If such disks are purchased together with a server, the system disk as well as the data disks you have configured to release with server will be deleted. For the data disks not configured to release with server, the system will prompt you whether to delete them when you delete the server. You can make the decision based on your service requirements.

- For yearly/monthly disks:
If the disks are purchased together with a server, they will be unsubscribed from when you unsubscribe from the server.

3.6 Will I Be Billed for the Disks in the Recycle Bin?


Yes, disks in the recycle bin are all billed on a pay-per-use basis. For details, see [Billing for EVS Recycle Bin](#).

The billing ends after the disks are permanently deleted.

To view the EVS recycle bin bill, do as follows:

- Step 1** Sign in to the [console](#).
- Step 2** Click **Billing** from the top menu bar to go to the Billing Center.
- Step 3** Choose **Billing > Transactions and Detailed Bills** and click the **Bill Details** tab.
- Step 4** Select a billing cycle, select **Usage** for **Settings**, and select **By billing cycle** for **Data Period**.
- Step 5** In the list, select **Elastic Volume Service (EVS)** for **Service Type**.
- Step 6** In the **Resource Tag** column, find the **_sys_recycle_bin_volume:true** tag, which identifies the EVS recycle bin bill.

Figure 3-1 Viewing the EVS recycle bin bill



NOTE

You can also click the **Export** button next to the search box to export all bills and find out the recycle bin bill by filtering the **_sys_recycle_bin_volume:true** tag.

----End

4 Attachment

4.1 Why Can't I View the Attached Data Disk on the Server?

Troubleshooting

Table 4-1 Possible causes

OS	Possible Cause	Solution
Linux	- New data disks are not formatted and partitioned by default. An unformatted disk will not be listed in the command output. You must manually initialize the disk. - If a data disk cannot be found after the server is restarted, automatic partition mounting at system start may not be configured.	Linux Data Disk
Windows	New data disks are not formatted and partitioned by default. Only formatted and partitioned drives show up in the resource manager. You must manually initialize the disk.	Windows Data Disk

Linux Data Disk

Symptom: A data disk has been attached to a Linux server on the console, but the disk cannot be viewed on the server.

Run **df -TH** to view the disk information. CentOS 7.4 is used in this example. The normal command output is as follows:

```
[root@ecs-test-0001 ~]# df -TH
Filesystem      Type      Size  Used Avail Use% Mounted on
/dev/vda1       ext4      43G   1.9G   39G   5% /
devtmpfs       devtmpfs  2.0G    0   2.0G   0% /dev
```

```
tmpfs      tmpfs    2.0G    0 2.0G    0% /dev/shm
tmpfs      tmpfs    2.0G   9.1M 2.0G    1% /run
tmpfs      tmpfs    2.0G    0 2.0G    0% /sys/fs/cgroup
tmpfs      tmpfs    398M    0 398M    0% /run/user/0
/dev/vdb1  ext4    106G   63M 101G    1% /mnt/sdc
```

Unlike the normal command output, only system disk **/dev/vda1** is visible, but data disk **/dev/vdb1** is missing from the command output.

Cause Analysis:

- **Cause 1:** New data disks are not formatted and partitioned by default. An unformatted disk will not be listed in the command output. You must manually initialize the disk.

For details about how to initialize data disks, see [Introduction to Data Disk Initialization Scenarios and Partition Styles](#).

- **Cause 2:** If a data disk cannot be found after the server is restarted, automatic partition mounting at system start may not be configured. Perform the following steps:

- a. Mount the data disk.

mount <disk-partition> <mount-point>

In this example, run the following command:

mount /dev/vdb1 /mnt/sdc

Perform the following steps to configure auto mount at system start:

- b. Query the partition UUID.

blkid <disk-partition>

In this example, the UUID of the **/dev/vdb1** partition is queried.

blkid /dev/vdb1

Information similar to the following is displayed:

```
[root@ecs-test-0001 ~]# blkid /dev/vdb1
/dev/vdb1: UUID="0b3040e2-1367-4abb-841d-ddb0b92693df" TYPE="ext4"
```

The UUID of the **/dev/vdb1** partition is displayed.

- c. Open the **fstab** file using the vi editor.

vi /etc/fstab

Press **i** to enter editing mode.

- d. Move the cursor to the end of the file and press **Enter**. Then, add the following information:

```
UUID=0b3040e2-1367-4abb-841d-ddb0b92693df /mnt/sdc      ext4    defaults    0 2
```

In this example, the line starting with "UUID" is the information added. Edit this line to match the following format:

- **UUID:** The UUID obtained in **b**.
- **Mount point:** The directory on which the partition is mounted. You can query the mount point using **df -TH**.
- **Filesystem:** The file system format of the partition. You can query the file system format using **df -TH**.
- **Mount option:** The partition mount option. Usually, this parameter is set to **defaults**.


- **Dump:** The Linux dump backup option.
 - **0:** Linux dump backup is not used. Usually, dump backup is not used, and you can set this parameter to **0**.
 - **1:** Linux dump backup is used.
 - **fsck:** The fsck option, which means whether to use fsck to check the disk during startup.
 - **0:** The fsck option is not used.
 - If the mount point is the root partition (/), this parameter must be set to **1**.
If this parameter is set to **1** for the root partition, this parameter for other partitions must start with **2** because the system checks the partitions in the ascending order of the values.
- e. Press **Esc**, enter **:wq**, and press **Enter**.
The system saves the configurations and exits the vi editor.
Verify that the disk is auto-mounted at startup.
- i. Unmount the partition.
umount <disk-partition>
In this example, run the following command:
umount /dev/vdb1
 - ii. Reload all the content in the **/etc/fstab** file.
mount -a
 - iii. Query the file system mounting information.
mount | grep <mount-point>
In this example, run the following command:
mount | grep /mnt/sdc
If information similar to the following is displayed, auto mount has taken effect:

```
root@ecs-test-0001 ~]# mount | grep /mnt/sdc  
/dev/vdb1 on /mnt/sdc type ext4 (rw,relatime,data=ordered)
```

Windows Data Disk

Symptom: A data disk has been attached to a Windows server on the console, but the disk cannot be viewed on the server. For example, Volume (D:) was not shown in **This PC** of a server running Windows Server 2012. Normally, Volume (D:) appears, as shown in [Figure 4-1](#).

Figure 4-1 Volume (D:) appears



Solution: New data disks are not formatted and partitioned by default. Only formatted and partitioned drives show up in **This PC**. You must manually initialize the disk before it can be viewed here.

For details about how to initialize data disks, see [Introduction to Data Disk Initialization Scenarios and Partition Styles](#).

4.2 Why Can't I Attach My Disk to a Server?

Symptom

My disk cannot be attached to a server.

Troubleshooting

Possible causes are listed here in order of their probability.

If the fault persists after you have ruled out one cause, move on to the next one in the list.

Table 4-2 Troubleshooting

Symptom	Solution
The target server cannot be found on the Attach Disk page.	- Go to Check Whether the Disk and Server Are in the Same AZ. - Cloud servers created from ISO images are only used for OS installation. They have limited functions and cannot have EVS disks attached.
The Attach button is grayed out.	- Go to Maximum Number of Disks That Can Be Attached to the Server Has Been Reached. - Go to Check Whether the Disk Has Been Added to a Replication Pair.

Symptom	Solution
An incorrect OS type warning is displayed when a shared disk is attached.	Go to Check Whether the Servers Attached with the Shared Disk Are Running the Same Type of OS .


Check Whether the Disk and Server Are in the Same AZ

Symptom: After you click **Attach**, the target server cannot be found on the **Attach Disk** page.

Solution: A disk can only be attached to a server in the same AZ and region. The **Attach Disk** page filters and shows all the servers that the disk can be attached to. Determine whether your disk data is required.

- If the disk data is no longer needed, delete or unsubscribe from the disk, and then purchase a new disk in the AZ where your target server is located.
- If the disk data is still required, create a new disk with the same data in the target AZ. The procedure is as follows:
 - a. Create a backup for the disk.

Figure 4-2 Create Backup



- b. Create a new disk from this backup. During the creation, select the target AZ. You can also change the settings of **Disk Type** and **Advanced Settings** if needed.
- c. After the disk is created, click **Attach**. Your target server is displayed on the **Attach Disk** page.

Maximum Number of Disks That Can Be Attached to the Server Has Been Reached

Symptom: The **Attach** button is grayed out.

Solution:

- Non-shared disk: When you hover the mouse over the **Attach** button, message "This operation can be performed only when the disk is in the Available state" is displayed.

A non-shared disk can only be attached to one server. If the disk status is **In-use**, the disk has been attached. You can detach the disk, wait until the disk status changes to **Available**, and then attach the disk to the target server.

- Shared disk: When you hover the mouse over the **Attach** button, message "This operation cannot be performed because the maximum number of servers that a shared disk can be attached to has been reached" is displayed.

A shared disk can be attached to a maximum of 16 servers, but you can detach the shared disk from one server and attach it to a new one if needed.

NOTE

Data may be lost after you detach an encrypted disk. For more information, see [If I Detach a Disk, Will I Lose the Data on My Disk?](#)

Check Whether the Disk Has Been Added to a Replication Pair

Symptom: The **Attach** button is grayed out. When you hover the mouse over the **Attach** button, message "This operation cannot be performed on a disk in a replication pair" is displayed.

Solution: Delete the replication pair and attach the disk again.

- To delete replication pairs created using synchronous replication, see [Deleting a Replication Pair](#).
- To delete replication pairs created using asynchronous replication, see [Deleting a Replica Pair](#)

Check Whether the Servers Attached with the Shared Disk Are Running the Same Type of OS

Symptom: After you click **Attach**, the target server cannot be selected on the **Attach Disk** page, and message "A shared disk must be attached to servers with the same OS type" is displayed.

Solution: This message indicates that the OS type of the target server is inconsistent with that of the servers attached with the shared disk. You can change the OS type based your service requirements.

Submitting a Service Ticket

If the problem persists, [submit a service ticket](#).

4.3 Can I Attach a Disk to Multiple Servers?

- A non-shared disk can only be attached to one server.
- A shared disk can be attached to up to 16 servers. For more information about shared disks, see [Managing Shared EVS Disks](#).

NOTE

- Shared disks are a type of EVS disks that can be attached to multiple servers.
- A shared file system or cluster management system must be set up before you can properly use a shared disk. If you simply attach a shared disk to multiple servers, data cannot be shared between those servers and may be overwritten.

4.4 Can I Attach a Disk to a Server in a Different AZ?

No.

Disks and the server you attach the disks to must be in the same AZ. The same is true for shared disks. A shared disk can only be attached to the servers in the same AZ.

If your disk and server are in different AZs, there are two scenarios:

- The disk is empty, or data on the disk is no longer needed.

Delete or unsubscribe from the disk according to [Unsubscribing from or Deleting an EVS Disk](#). Then, buy a new disk in the AZ where the server belongs.

- Data on the disk is required.

Create a backup for the disk using the CBR service. Then, use this backup to create a new disk in the AZ where the server is. For details, see [Creating a Cloud Disk Backup](#) and [Creating a Disk from a Cloud Disk Backup](#).

4.5 How Can I Add a Data Disk to an Existing Server?

Data disks can be purchased during or after the server purchase. If you purchase data disks during the server purchase, the system will automatically attach the data disks to the server. If you purchase data disks after the server purchase, you need to manually attach the data disks.

- On a Windows server:
 - If a data disk is purchased along with the server, you need to log in to the server and initialize the disk. The data disk will be visible after the initialization succeeds.
 - If no data disk is purchased along with the server, you need to purchase a data disk and attach it to the server. Then, you need to log in to the server and initialize the disk. The data disk will be visible after the initialization succeeds.
- On a Linux server:
 - If a data disk is purchased along with the server, you need to log in to the server and initialize the disk. The data disk will be visible after the initialization succeeds and the disk has been mounted via the **mount** command.
 - If no data disk is purchased along with the server, you need to purchase a data disk and attach it to the server. Then, you need to log in to the server and initialize the disk. The data disk will be visible after the initialization succeeds and the disk has been mounted via the **mount** command.

For details about how to initialize data disks, see [Introduction to Data Disk Initialization Scenarios and Partition Styles](#).

4.6 Can I Attach a Yearly/Monthly Disk to Another Server?

If the disk is purchased along with a server and they both part of the same order, the disk cannot be attached to another server.

If the disk was purchased on the EVS console and not as part of the same order as any server, it can be attached to another server.

4.7 Can I Attach Different Types of Disks to the Same Server?

Yes. Different types of EVS disks can be attached to the same server. You only need to make sure that these disks and the server are in the same AZ.

4.8 Can I Switch Between System Disks and Data Disks?

Whether you can switch between system and data disks depends on the disk billing mode.

NOTE

- If you detach a system disk and then attach it to another server as a data disk, the maximum capacity of this disk is still 1 TiB.
- If you detach a system disk and then attach it to another server as a system disk, ensure that this server uses the same image as the original server.

Pay-per-Use Disks

Table 4-3 Detaching and reattaching of pay-per-use EVS disks

Original Use	Target Server	New Use	Supported
System disk (It becomes a bootable disk after being detached.)	Attach to the same server	System disk	√
		Data disk	√
	Attach to another server	System disk	√
		Data disk	√
Data disk	Attach to the same server	System disk	×
		Data disk	√
	Attach to another server	System disk	×
		Data disk	√

Yearly/Monthly Disks

- Yearly/monthly EVS disks purchased together with a yearly/monthly server belong to the same order and are in a binding relationship. After such EVS disks are detached, they cannot be re-attached to other servers.
 - You can detach such a system disk and then re-attach it to the same server as a system disk or data disk.
 - You can detach such a data disk and then re-attach it to the same server as a data disk.
- Yearly/monthly EVS disks that are separately purchased can serve as data disks only. You can detach such a disk and then re-attach it to the same server or other servers as a data disk.

4.9 What Should I Do If a Linux EVS Disk Is Attached to a Windows Server?

You are advised not to attach a Linux EVS disk to a Windows server or attach a Windows EVS disk to a Linux server.

The disk information may fail to be displayed due to the inconsistent file systems. To solve this issue, you need to initialize and partition the disk again. Formatting the disk will destroy any data the disk has contained, so you should back up the data first.

4.10 Can I Attach an EVS Disk Purchased with a Yearly/Monthly Server to Another Yearly/Monthly Server?

No.

A yearly/monthly disk purchased together with a yearly/monthly server is in a binding relationship with the server. It cannot be attached to other servers.

4.11 Can I Change the Function of a System Disk or Data Disk Purchased Along with a Server?

This section describes how to change the function of a disk on the original server. To change the function of a disk and use it on a different server, see [Can I Switch Between System Disks and Data Disks?](#)

- System disk purchased along with a server: You can detach the system disk and then re-attach it to the same server as a system disk or data disk.

NOTE

Each server can only have one system disk. If there is already a system disk attached to the server, then the detached system disk cannot be attached as a second system disk.

- Data disk purchased along with a server: You can detach the data disk and then re-attach it to the same server only as a data disk. It cannot be attached as a system disk.

4.12 How Do I Obtain My Disk Device Name in the ECS OS Using the Device Identifier Provided on the Console?

Scenarios

You find that the device name displayed in the ECS OS is different from that displayed on the management console and you cannot determine which disk name is correct. This section describes how to obtain the disk name used in an ECS OS according to the device identifier on the console.

For details about how to attach disks, see [Attaching a Disk to an ECS](#).

Obtaining the Disk ID of an ECS on the Console

1. Log in to the management console.
2. Choose **Compute** > **Elastic Cloud Server**.
3. Click the target ECS name in the ECS list.
The ECS details page is displayed.
4. Click the **Disks** tab and then click  to expand the disk information.
5. Check the device type and ID of the disk.

NOTE

If **Device Identifier** is not displayed on the page, stop the ECS and restart it.

- KVM ECS
 - If **Device Type** is **VBD**, use a serial number or BDF to obtain the disk device name. (Kunpeng ECSs only support serial numbers to obtain disk device names.)
If you use a serial number (recommended) to obtain the disk device name, see [Using a Serial Number to Obtain the Disk Device Name \(Windows\)](#) and [Using a Serial Number to Obtain a Disk Device Name \(Linux\)](#).
If you use a BDF to obtain the disk device name, see [Using a BDF to Obtain a Disk Device Name \(Linux\)](#). (BDF cannot be used to obtain the disk device name of Windows ECSs.)
 - If **Device Type** is **SCSI**, use a WWN to obtain the disk device name.
For details, see [Using a WWN to Obtain the Disk Name \(Windows\)](#) and [Using a WWN to Obtain a Disk Device Name \(Linux\)](#).
- QingTian ECS
For QingTian ECSs such as C7 or M7 series, the **Device Type** is **VBD** or **SCSI**, and the device ID is **WWN**. You can use the WWN to obtain the disk device name of the ECS. For details, see [Using a WWN to Obtain the Disk Name \(Windows\)](#) and [Using a WWN to Obtain a Disk Device Name \(Linux\)](#).

- Xen ECS
 - For details, see [Obtaining the Disk Device Name of a Xen Instance](#).

Using a Serial Number to Obtain the Disk Device Name (Windows)

If a serial number is displayed on the console, use either of the following methods to obtain the disk name.

cmd

1. Start **cmd** in a Windows OS as an administrator and run either of the following commands:

wmic diskdrive get serialnumber

wmic path win32_physicalmedia get SerialNumber

wmic path Win32_DiskDrive get SerialNumber

NOTE

A serial number is the first 20 digits of a disk UUID.

For example, if the serial number of a VBD disk on the console is 97c876c0-54b3-460a-b, run either of the following commands to obtain the serial number of the disk on the ECS OS:


wmic diskdrive get serialnumber

wmic path win32_physicalmedia get SerialNumber

wmic path Win32_DiskDrive get SerialNumber

The following information is displayed.

Figure 4-3 Obtaining the disk serial number



```
C:\Users\Administrator>wmic diskdrive get serialnumber
SerialNumber
97c876c0-54b3-460a-b


C:\Users\Administrator>wmic path win32_physicalmedia get SerialNumber
SerialNumber
97c876c0-54b3-460a-b

C:\Users\Administrator>wmic path Win32_DiskDrive get SerialNumber
SerialNumber
97c876c0-54b3-460a-b
```

2. Run the following command to check the disk corresponding to the serial number:

wmic diskdrive get Name, SerialNumber

Figure 4-4 Checking the disk corresponding to the serial number




```
C:\Users\Administrator>wmic diskdrive get Name, SerialNumber
Name                      SerialNumber
\\.\PHYSICALDRIVE0        97c876c0-54b3-460a-b
```

PowerShell

1. Start PowerShell as an administrator in a Windows OS.
2. Run the following command to check the disk on which the logical disk is created:
 - Windows Server 2012 or later
 - i. Run the following command to check the disk on which the logical disk is created:
Get-CimInstance -ClassName Win32_LogicalDiskToPartition | select Antecedent, Dependent | fl
As shown in [Figure 4-5](#), the disk is **Disk 0**.
 - ii. Run the following command to view the mapping between the serial number and the disk:
Get-Disk |select Number, SerialNumber
As shown in [Figure 4-5](#), the disk is **Disk 0**.

Figure 4-5 Viewing the disk on which the logical disk is created



```
PS C:\Users\Administrator> Get-CimInstance -ClassName Win32_LogicalDiskToPartition |select Antecedent, Dependent | fl
Antecedent : Win32_DiskPartition (DeviceID = "Disk #0, Partition #1")
Dependent  : Win32_LogicalDisk (DeviceID = "C:")

PS C:\Users\Administrator> Get-Disk |select Number, SerialNumber
Number SerialNumber
-----
0 97c876c0-54b3-460a-b1d5-f616520d39517815206127
1 dswfal6520d39517815206127
```

- Versions earlier than Windows 2012
 - i. Run the following command to check the disk on which the logical disk is created:
Get-WmiObject -Class Win32_PhysicalMedia |select Tag, Serialnumber
 - ii. Run the following command to view the mapping between the serial number and the disk:
Get-WmiObject -Class Win32_LogicalDiskToPartition |select Antecedent, Dependent | fl

Using a Serial Number to Obtain a Disk Device Name (Linux)

If a serial number is displayed on the console, run either of the following commands to obtain the device name.

```
udevadm info --query=all --name=/dev/xxx | grep ID_SERIAL
ll /dev/disk/by-id/*
```

NOTE

A serial number is the first 20 digits of a disk UUID.

For example, if the serial number of the VBD disk is 62f0d06b-808d-480d-8, run either of the following commands:

```
udevadm info --query=all --name=/dev/vdb | grep ID_SERIAL
ll /dev/disk/by-id/*
```

The following information is displayed:

```
[root@ecs-ab63 ~]# udevadm info --query=all --name=/dev/vdb | grep ID_SERIAL
E: ID_SERIAL=62f0d06b-808d-480d-8
[root@ecs-ab63 ~]# ll /dev/disk/by-id/*
lrwxrwxrwx 1 root root 9 Dec 30 15:56 /dev/disk/by-id/virtio-128d5bfd-f215-487f-9 -> ../../vda
lrwxrwxrwx 1 root root 10 Dec 30 15:56 /dev/disk/by-id/virtio-128d5bfd-f215-487f-9-part1 -> ../../vda1
lrwxrwxrwx 1 root root 9 Dec 30 15:56 /dev/disk/by-id/virtio-62f0d06b-808d-480d-8 -> ../../vdb
```

/dev/vdb is the disk device name.

Using a BDF to Obtain a Disk Device Name (Linux)

1. Run the following command to use a BDF to obtain the device name:

```
ll /sys/bus/pci/devices/BDF disk ID/virtio*/block
```

For example, if the BDF disk ID of the VBD disk is 0000:02:02.0, run the following command to obtain the device name:

```
ll /sys/bus/pci/devices/0000:02:02.0/virtio*/block
```

The following information is displayed:

```
[root@ecs-ab63 ~]# ll /sys/bus/pci/devices/0000:02:02.0/virtio*/block
total 0
drwxr-xr-x 8 root root 0 Dec 30 15:56 vdb
```

/dev/vdb is the disk device name.

Using a WWN to Obtain the Disk Name (Windows)

1. Obtain the device identifier on the console by referring to [Obtaining the Disk ID of an ECS on the Console](#).
2. Manually convert the WWN.

For example, the obtained WWN (device identifier) is 688860300003252ffa16520d39517815.


- a. Obtain the 21st to 17th digits that are counted backwards (**3252f**).
- b. Convert a hexadecimal (**3252f**) to a decimal (**206127**).

3. Start PowerShell as an administrator in a Windows OS.
4. Run the following command:

```
Get-CimInstance Win32_DiskDrive | Select-Object DeviceID, SerialNumber
```

5. In the command output, the disk whose serial number ends with **206127** is the disk corresponding to the WWN.

Figure 4-6 Disk with the serial number ending with **206127**



```
PS C:\Users\Administrator> Get-CimInstance Win32_DiskDrive | Select-Object DeviceID, SerialNumber
DeviceID                               SerialNumber
-----
\\.\PHYSICALDRIVE0                     97c876c0-54b3-460a-b
\\.\PHYSICALDRIVE1                     dswfa16520d39517815206127
```

Using a WWN to Obtain a Disk Device Name (Linux)

1. Log in to the ECS as user **root**.
2. Run the following command to view the disk device name:

```
ll /dev/disk/by-id |grep WWN|grep scsi-3
```

For example, if the WWN obtained on the console is 6888603000008b32fa16688d09368506, run the following command:

```
ll /dev/disk/by-id |grep 6888603000008b32fa16688d09368506|grep scsi-3
```

The following information is displayed:

```
[root@host-192-168-133-148 block]# ll /dev/disk/by-id/ |grep 6888603000008b32fa16688d09368506 |  
grep scsi-3  
lrwxrwxrwx 1 root root 9 May 21 20:22 scsi-36888603000008b32fa16688d09368506 -> ../../sda
```

Obtaining the Disk Device Name of a Xen Instance

Step 1 Obtain the disk information displayed on the console.

1. Log in to the management console.
2. Choose **Compute > Elastic Cloud Server**.
3. Click the target ECS name in the ECS list.
The ECS details page is displayed.
4. Click the **Disks** tab and then click  to expand the disk information.
5. Check the device name, type, and ID of the disk.
 - If the device type is **VBD**, go to step [Step 2](#).
 - If the device type is **SCSI**, go to step [Step 3](#).

NOTE

If **Device Identifier** is not displayed on the page, stop the ECS and restart it.

Step 2 Check the device name attached to the VBD disk in the ECS.

For a VBD disk, the device name displayed on the management console corresponds to the disk device name in the ECS OS. For details, see [Table 4-4](#).

Table 4-4 Mapping between disk device names displayed on the management console and those obtained on the ECS

Device Name (on Management Console)	Device Name (in ECS)
/dev/sd***	/dev/xvd***
/dev/vd***	/dev/xvd***
/dev/xvd***	/dev/xvd***

An example is provided as follows:

If the device name displayed on the management console is **/dev/sdb**, the device name of the device attached to the ECS is **/dev/xvdb**.

Step 3 Check the device name of the SCSI disk attached to the ECS.

1. Obtain the disk device ID.
The device ID of the SCSI disk is the disk WWN on the ECS.

2. Log in to the ECS as user **root**.
3. Run the following command to view the disk device name:

```
ll /dev/disk/by-id |grep WWWgrep scsi-3
```

```
[root@host-192-168-133-148 block]# ll /dev/disk/by-id/ |grep 6888603000008b32fa16688d09368506 |  
grep scsi-3  
lrwxrwxrwx 1 root root 9 May 21 20:22 scsi-36888603000008b32fa16688d09368506 -> ../../sda
```

----End

4.13 How Can I View Data on My Disk If Its Yearly/ Monthly Server Has Expired?

You can purchase a pay-per-use server in the same region and AZ of the disk, attach the disk to this server, and log in to the server to view the data on the disk.

NOTICE

Do not initialize the disk. Or, the data on the disk will be cleared.

5 Capacity Expansion

5.1 Can I Reduce or Temporarily Expand the Disk Capacity?

Once a disk is created, you cannot directly reduce its capacity. However, you can migrate your server using Server Migration Service (SMS) and [reduce the disk capacity](#) during the migration.

5.2 What Are the Differences Between Expanding Capacity by Expanding an EVS Disk and Creating a New EVS Disk?

The differences are as follows:

- Expanding an EVS disk is when you expand the capacity of an existing EVS disk. Some systems let you expand the capacity of EVS disks in use. In this case, services are not interrupted.
- If you create a new EVS disk and attach it to a server that already has an existing EVS disk, the new EVS disk and the original EVS disk are attached to the same server but independent from each other.

5.3 Will My Disk Data Be Lost After I Expand the Disk Capacity?

Data will not be deleted during a system disk or data disk capacity expansion. However, incorrect operations during an expansion may result in data loss or exceptions. You are advised to back up the disk data before expanding capacity.

- For details about disk backups, see [Cloud Backup and Recovery User Guide](#).
- For details about disk snapshots, see [Creating a Snapshot](#).

5.4 Can I Use Backups or Snapshots Created Before Capacity Expansion to Restore Data on Expanded Disks?

Yes. If backups or snapshots have been created for disks before capacity was expanded, you can restore your disk data from these backups or snapshots after the capacity is expanded. Expansion operations do not affect backups and snapshots.

After the disk data is restored, the disk capacity is increased, but the additional space still needs to be partitioned and formatted before it can be used. You must log in to the server to extend the disk partition or file system.

To extend disk partitions and file systems, see the following sections:

- [Extending Disk Partitions and File Systems \(Windows\)](#)
- [Extending Disk Partitions and File Systems \(Linux\)](#)

5.5 Do I Need to Restart the Server After Expanding the Disk Capacity?

An EVS disk can be expanded either in the **Available** or **In-use** state. Expanding the disk capacity on the console enlarges the disk capacity, but you still need to log in to the server and extend the disk partitions and file systems to make that additional space usable. You may need to restart the server during the partition and file system extension. The details are as follows:

- After expanding an **In-use** disk on the console, log in to the server and view the disk capacity.
 - If the additional space can be viewed, you can extend the partition and file system and a restart is not required.
 - If the additional space cannot be viewed, the server OS may not be included in the [compatibility list](#). In this case, you should stop and then start the server (do not restart the server). When the additional space can be viewed, extend the partition and file system.
- After expanding an **Available** disk on the console, attach the disk to the server and extend the partition and file system on the server. In this case, a server restart is not required.

5.6 Do I Need to Detach an EVS Disk Before Expanding Its Capacity?

An expansion consists of two phases:

1. Expand the disk capacity on the console.
 - A shared, in-use disk cannot be expanded. You must detach the shared disk from all its servers and then expand its capacity.

- A non-shared, in-use disk can be expanded, and you can leave the disk attached during expansion as long as the following conditions are met:
 - The disk's server is in the **Running** or **Stopped** state.
 - The disk's server OS supports capacity expansion of **In-use** disks.

 NOTE

Only some server OSs support capacity expansion of **In-use** disks. For details, see [Expanding Capacity for an In-use EVS Disk](#).

2. Log in to the server and create a new partition or allocate the additional space to one that is already there.

The unmount operation is not required, either for Windows or Linux.

5.7 What Should I Do If My Disk Capacity Exceeds 2 TiB After Expansion?

An EVS system disk can be as large as 1 TiB (1,024 GiB). You can expand the capacity of a system disk to up to 1 TiB.

An EVS data disk can be as large as 32 TiB (32,768 GiB).

- With MBR, any disk space in excess of 2 TiB cannot be allocated and used, because the maximum disk capacity supported by MBR is 2 TiB (2,048 GiB).
In this case, if you want to expand the disk capacity to over 2 TiB, change the partition style from MBR to GPT. Ensure that the disk data has been backed up before changing the partition style because services will be interrupted and data on the disk will be deleted during this change.
- With GPT, you can expand the capacity of a data disk to up to 32 TiB because the maximum disk capacity supported by GPT is 18 EiB (19,327,352,832 GiB).

To extend disk partitions and file systems, see the following sections:

- [Extending Disk Partitions and File Systems \(Windows\)](#)
- [Extending Disk Partitions and File Systems \(Linux\)](#)

5.8 How Can I Allocate Newly Added Space to a New Partition?

Windows

In Windows, if you already have a D drive and want to add an E drive, refer to the following:

The "Creating a New Partition" part in [Extending Disk Partitions and File Systems \(Windows\)](#).

Linux

In Linux, if your disk already has, for example, partition **/dev/vdb1** and you want to create a new partition, **/dev/vdb2**, and allocate the additional space to the new partition, refer to the following:

The "Creating a New MBR Partition" and "Creating a New GPT Partition" parts in [Extending Disk Partitions and File Systems \(Linux\)](#)

5.9 How Can I Allocate Newly Added Space to an Existing Partition?

Windows

In Windows, if your disk already has, for example, a D drive and you want to add space to this drive, refer to the following:

The "Extending an Existing Partition" part in [Extending Disk Partitions and File Systems \(Windows\)](#)

Linux

In Linux, if your disk already has, for example, partition `/dev/vdb1` and you want to add space to this partition, refer to the following:

The "Extending an Existing Partition" part in [Extending Disk Partitions and File Systems \(Linux\)](#)

5.10 Why Did My Disk Capacity Remain Unchanged on the Server After a Capacity Expansion?

After expanding disk capacity on the console, you must log in to the server and extend the disk partition and file system for the extra capacity to become available. Otherwise, you cannot view the additional space on the server.

5.11 Why Can't I Expand Capacity for My Disk?

Symptom

Capacity expansion is not allowed for the disk.

Troubleshooting

Possible causes are listed here in order of their probability.

If the fault persists after you have ruled out one cause, move on to the next one in the list.

Figure 5-1 Troubleshooting




Table 5-1 Possible causes

Possible Cause	Solution	Reference
A yearly/monthly disk has a renewal order that has not taken effect.	1. Unsubscribe from the renewal. 2. Expand the disk capacity. 3. Renew the disk.	Yearly/Monthly Disk Has a Renewal Order That Has Not Taken Effect
A yearly/monthly disk has an unpaid expansion order.	Pay for or cancel the capacity expansion order.	Yearly/Monthly Disk Has An Unpaid Expansion Order
A shared disk is still attached to a server.	Detach the disk from all the servers.	Shared Disk Is Still Attached to a Server

Yearly/Monthly Disk Has a Renewal Order That Has Not Taken Effect

What Is a Renewal Order That Has Not Taken Effect?

For example, a user has purchased a yearly/monthly disk, and the disk expired on December 30, 2019, if the user renewed the disk on December 15, 2019, the order is a renewal order that will not take effect before December 30, 2019.

Symptom: A message is displayed in the upper right corner of the console, indicating that the disk cannot be expanded because it has a renewal order that has not taken effect.

Solution: Cancel the renewal order, expand the disk capacity, and renew the disk again.

Step 1 Sign in to the console and click **Billing** in the upper right corner.

Step 2 Locate the target order and choose **More > Unsubscribe from Renewal** in the **Operation** column.

Step 3 After the unsubscription is complete, go to the EVS console and expand the disk capacity.

Step 4 Renew the disk after the capacity expansion succeeded.

----End

Yearly/Monthly Disk Has An Unpaid Expansion Order

Symptom: The **Expand Capacity** button is grayed out and the following hover tip is displayed: This operation cannot be performed because the disk has unpaid orders.

Solution: Pay for or cancel the capacity expansion order.

Step 1 On the EVS console, click **Unpaid** in the **Status** column.

The order details page is displayed.

Step 2 Click **Pay** or **Cancel Order**.

Step 3 Return to the EVS disk list. If the **Expand Capacity** button is available, the operation is successful.

----End

Shared Disk Is Still Attached to a Server

Symptom: The **Expand Capacity** button is grayed out. When you attempt to click the capacity expansion button, the following hover tip is displayed: This operation can be performed only when the shared disk is in the Available state.

Solution: Detach the disk from all servers. If the **Expand Capacity** button becomes available, you can expand the disk capacity.

Submitting a Service Ticket

If the problem persists, [submit a service ticket](#).

5.12 How Do I Extend the File System of an Unpartitioned Data Disk in Linux?

Scenarios

If no partition but only a file system is created on a data disk, extend the file system according to the following operations:

Run the **lsblk** command. Information similar to the following is displayed:

```
[root@ecs-test ~]# lsblk
NAME        MAJ:MIN RM  SIZE RO TYPE MOUNTPOINT
vda         253:0    0   40G  0 disk 
└─vda1      253:1    0   40G  0 part /
vdb         253:16   0   60G  0 disk /mnt/sdc
```

In the command output, no partition but only a file system is created on data disk **/dev/vdb**.

In the following example, CentOS 7.4 64bit is used as the example OS, data disk **/dev/vdb** has 10 GiB, no partition but only a file system is created on the

disk, and additional 50 GiB has been added to this data disk on the console. The following steps show how to extend this 50 GiB to the file system.

- [Extending the EXT* File System](#)
- [Extending the XFS File System](#)

The way you allocate additional space depends on the OS. This example is used for reference only. For detailed operations and differences, see the corresponding OS documents.

Extending the EXT* File System

Step 1 Run the following command to extend the file system:

```
resize2fs <disk-name>
```

In this example, run the following command:

```
resize2fs /dev/vdb
```

Information similar to the following is displayed:

```
[root@ecs-test ~]# resize2fs /dev/vdb
resize2fs 1.42.9 (28-Dec-2013)
Filesystem at /dev/vdb is mounted on /root/test; on-line resizing required
old_desc_blocs = 2, old_desc_blocs = 8
[17744.521535] EXT4-fs (vdb): resizing filesystem from 26214400 to 15728640 blocks
[17744.904470] EXT4-fs (vdb): resized filesystem to 15728640
The filesystem on /dev/vdb is now 15728640 blocks long.
```

Step 2 Run the following command to view the result:

```
df -TH
```

Information similar to the following is displayed:

```
[root@ecs-test ~]# df -TH
Filesystem      Type      Size      Used Avail Use% Mounted on
/dev/vda1       ext4       43G      1.9G   39G    5% /
devtmpfs        devtmpfs   2.0G      0      2.0G    0% /dev
tmpfs           tmpfs      2.0G      0      2.0G    0% /dev/shm
tmpfs           tmpfs      2.0G      9.1M    2.0G    1% /run
tmpfs           tmpfs      2.0G      0      2.0G    0% /sys/fs/cgroup
tmpfs           tmpfs      398M      0      398M    0% /run/user/0
/dev/vdb        ext4       64G      55M     61G    1% /mnt/sdc
```

----End

Extending the XFS File System

Step 1 Run the following command to extend the file system:

```
xfs_growfs <disk-name>
```

In this example, run the following command:

```
xfs_growfs /dev/vdb
```

Information similar to the following is displayed:

```
[root@ecs-test ~]# xfs_growfs /dev/vdb
meta-data=/dev/vdb          isize=512    agcount=4, agsize=655360 blks
      =                       sectsz=512   attr=2, projid32bit=1
```

```
=          crc=1      finobt=0, spinodes=0
data =      bsize=4096  blocks=2621440, imaxpct=25
=          sunit=0     swidth=0 blks
naming =version2      bsize=4096  ascii-ci=0 ftype=1
log  =internal      bsize=4096  blocks=2560, version=2
=          sectsz=512   sunit=0 blks, lazy-count=1
realtime =none        extsz=4096  blocks=0, rtextents=0
data blocks changed from 2621440 to 15728640.
```

Step 2 Run the following command to view the result:

df -TH

Information similar to the following is displayed:

```
[root@ecs-test ~]# df -TH
Filesystem      Type      Size  Used Avail Use% Mounted on
/dev/vda1       ext4      40G   2.3G   35G    7% /
devtmpfs        devtmpfs  1.9G   0   1.9G    0% /dev
tmpfs           tmpfs     1.9G   0   1.9G    0% /dev/shm
tmpfs           tmpfs     1.9G   8.6M   1.9G    1% /run
tmpfs           tmpfs     1.9G   0   1.9G    0% /sys/fs/cgroup
tmpfs           tmpfs     379M   0   379M    0% /run/user/0
/dev/vdb        xfs       60G   34M   60G    1% /mnt/sdc
```

----End

5.13 How Do I Extend the Root Partition of a Quickly Provisioned BMS?

Scenarios

If the root partition of your quickly provisioned BMS is too small, extend the root partition by referring to the following procedure.

This example uses CentOS 7.3 and system disk, **/dev/sdf**. The way you allocate additional space depends on the OS. This example is used for reference only. For detailed operations and differences, see the corresponding OS documents.

In this example, the initial size of the BMS system disk (**sdf**) is 40 GiB and needs to be expanded to 140 GiB. The initial disk partitions are as follows:

```
sdf      8:80    0    40G    0 disk
├─sdf1    8:81    0    500M    0 part /boot
├─sdf2    8:82    0     5G    0 part [SWAP]
├─sdf3    8:83    0   34.5G    0 part /
└─sdf4    8:84    0    64M    0 part
```

Procedure

Step 1 Access the EVS console and expand the system disk capacity to 140 GiB.

Step 2 Log in to the BMS and run the following command to view the system disk capacity:

lsblk

Information similar to the following is displayed:

```
sdf      8:80      0    140G      0 disk
├─sdf1    8:81      0    500M      0 part  /boot
├─sdf2    8:82      0      5G      0 part  [SWAP]
├─sdf3    8:83      0   34.5G      0 part  /
└─sdf4    8:84      0    64M      0 part
```

The system disk (**sdf**) has been expanded from 40 GiB to 140 GiB. The **sdf4** partition (64 MiB) is the configdriver partition that stores the BMS configuration information.

Step 3 Run the following command to back up the configdriver partition:

```
dd if=/dev/sdf4 of=/root/configdriver.img
```

Information similar to the following is displayed:

```
[root@bms-6acd ~]# dd if=/dev/sdf4 of=/root/configdriver.img
131072+0 records in
131072+0 records out
67108864 bytes (67 MB) copied, 0.291739 s, 230 MB/s
```

Step 4 Run the following command and delete the configdriver partition:

```
fdisk /dev/sdf
```

```
[root@bms-6acd ~]# fdisk /dev/sdf
Welcome to fdisk (util-linux 2.23.2).

Changes will remain in memory only, until you decide to write them.
Be careful before using the write command.

Command (m for help): d
Partition number (1-4, default 4): 4
Partition 4 is deleted

Command (m for help): w
The partition table has been altered!

Calling ioctl() to re-read partition table.

WARNING: Re-reading the partition table failed with error 16: Device or resource
busy.
The kernel still uses the old table. The new table will be used at
the next reboot or after you run partprobe(8) or kpartx(8)
Syncing disks.
```

Step 5 Run the **partprobe** command to update the partition information.

If partition configdriver has been deleted, information similar to the following is displayed:

```
sdf      8:80      0    140G      0 disk
├─sdf1    8:81      0    500M      0 part  /boot
├─sdf2    8:82      0      5G      0 part  [SWAP]
├─sdf3    8:83      0   34.5G      0 part  /
└─sdf4    8:84      0    97.7M      0 part
```

Step 6 Recreate the configdriver partition with 100 MB.

If the available sectors range from 83755008 to 293601279, set 293401279 (293601279 – 200000) as the new partition's first sector and 293601279 (default value) as the last sector.

```
Command (m for help): n
Partition type:
   p   primary (3 primary, 0 extended, 1 free)
   e   extended
Select (default e): p
Selected partition 4
First sector (83755008-293601279, default 83755008): 293401279
Last sector, +sectors or +size{K,M,G} (293401279-293601279, default 293601279):
Using default value 293601279
Partition 4 of type Linux and of size 97.7 MiB is set

Command (m for help): w
The partition table has been altered!

Calling ioctl() to re-read partition table.

WARNING: Re-reading the partition table failed with error 16: Device or resource
busy.
The kernel still uses the old table. The new table will be used at
the next reboot or after you run partprobe(8) or kpartx(8)
Syncing disks.
```

Run the **partprobe** command to update the partition information.

```
sdf      8:80      0    140G    0 disk
├─sdf1    8:81      0    500M    0 part  /boot
├─sdf2    8:82      0      5G    0 part  [SWAP]
├─sdf3    8:83      0   34.5G    0 part  /
└─sdf4    8:84      0    97.7M    0 part
```

Step 7 Run the following command to extend the root partition:

growpart /dev/sdf 3

Information similar to the following is displayed:

```
[root@bms-6acd ~]# growpart /dev/sdf 3
CHANGED: partition=3 start=11511808 old: size=72243200 end=83755008 new: size=28
1889471,end=293401279
```

Run the **lsblk** command to view the new root partition size.

```
sdf      8:80      0    140G    0 disk
├─sdf1    8:81      0    500M    0 part  /boot
├─sdf2    8:82      0      5G    0 part  [SWAP]
├─sdf3    8:83      0  134.4G    0 part  /
└─sdf4    8:84      0    97.7M    0 part
```

Step 8 Run the following command to extend the file system of the root partition:

resize2fs /dev/sdf3

Information similar to the following is displayed:

```
[root@bms-6acd ~]# resize2fs /dev/sdf3
resize2fs 1.42.9 (28-Dec-2013)
Filesystem at /dev/sdf3 is mounted on /: on-line resizing required
old_desc_blocks = 5, new_desc_blocks = 17
The filesystem on /dev/sdf3 is now 35236183 blocks long.

You have new mail in /var/spool/mail/root
[root@bms-6acd ~]# df -h
Filesystem      Size  Used Avail Use% Mounted on
/dev/sdf3       133G  1.9G  125G   2% /
devtmpfs        63G   0    63G   0% /dev
tmpfs           63G   0    63G   0% /dev/shm
tmpfs           63G  9.0M   63G   1% /run
tmpfs           63G   0    63G   0% /sys/fs/cgroup
/dev/sdf1       477M  104M  344M  24% /boot
tmpfs          13G   0    13G   0% /run/user/0
```

Step 9 Run the following command to restore the content of the configdriver partition:

```
dd if=/root/configdriver.img of=/dev/sdf4
```

Information similar to the following is displayed:

```
[root@bms-6acd ~]# dd if=/root/configdriver.img of=/dev/sdf4
131072+0 records in
131072+0 records out
67108864 bytes (67 MB) copied, 0.372614 s, 180 MB/s
[root@bms-6acd ~]#

/dev/sdf1: UUID="b9c472f9-6737-4200-910a-efa3af16629a" TYPE="ext4"
/dev/sdf2: UUID="b07ff4d0-8b0b-4c43-a40a-0b27290ea215" TYPE="swap"
/dev/sdf3: UUID="1e57f71e-6adc-4e98-9407-0f7d678d4525" TYPE="ext4"
/dev/sdf4: UUID="2018-09-27-19-13-01-00" LABEL="config-2" TYPE="iso9660"
[root@bms-6acd ~]#
```

The root partition of the quickly provisioned BMS has been extended.

----End

5.14 How Do I Check the Disk Partition Style in Linux?

You can use either fdisk or parted to check the disk partition style.

- [Method 1: Check Partition Style and File System Format Using fdisk](#)
- [Method 2: Check Partition Style and File System Format Using parted](#)

Method 1: Check Partition Style and File System Format Using fdisk

Step 1 Run the following command to view all the disks attached to the server:

```
lsblk
```

Information similar to the following is displayed:

```
[root@ecs-test-0001 ~]# lsblk
NAME MAJ:MIN RM SIZE RO TYPE MOUNTPOINT
vda 253:0 0 40G 0 disk
└─vda1 253:1 0 40G 0 part /
vdb 253:16 0 150G 0 disk
└─vdb1 253:17 0 100G 0 part /mnt/sdc
```

In this example, data disk **/dev/vdb** already has partition **/dev/vdb1** before capacity expansion, and the additional 50 GiB added has not been allocated yet. Therefore, **/dev/vdb** has 150 GiB, and **/dev/vdb1** has 100 GiB.

NOTE

If you run **lsblk** and find out that disk **/dev/vdb** has no partitions, format the disk by referring to [How Do I Extend the File System of an Unpartitioned Data Disk in Linux?](#) Otherwise, the additional space cannot be used after expansion.

Step 2 Run the following command to view the current disk partition style:

fdisk -l

Information similar to the following is displayed:

```
[root@ecs-test-0001 ~]# fdisk -l
```

```
Disk /dev/vda: 42.9 GiB, 42949672960 bytes, 83886080 sectors
Units = sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disk label type: dos
Disk identifier: 0x000bcb4e
```

Device	Boot	Start	End	Blocks	Id	System
/dev/vda1	*	2048	83886079	41942016	83	Linux

```
Disk /dev/vdb: 161.1 GiB, 161061273600 bytes, 314572800 sectors
Units = sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disk label type: dos
Disk identifier: 0x38717fc1
```

Device	Boot	Start	End	Blocks	Id	System
/dev/vdb1		2048	209715199	104856576	83	Linux

The value in the **System** column indicates the disk partition style. Value **Linux** indicates the MBR partition style. Value **GPT** indicates the GPT partition style.

- If the disk partitions displayed are inconsistent with those obtained in [Step 1](#), the possible reason may be that existing partitions use GPT and there is unallocated disk space. In this case, you cannot query all the partitions using **fdisk -l**. Go to [Method 2: Check Partition Style and File System Format Using parted](#).
- If the disk partitions displayed are consistent with those obtained in [Step 1](#), continue with the following operations.

Step 3 Run the following command to view the partition's file system format:

blkid <disk-partition>

In this example, run the following command:

blkid /dev/vdb1

```
[root@ecs-test-0001 ~]# blkid /dev/vdb1
/dev/vdb1: UUID="0b3040e2-1367-4abb-841d-ddb0b92693df" TYPE="ext4"
```

In the command output, the **TYPE** value is **ext4**, indicating that **/dev/vdb1**'s file system format is **ext4**.

Step 4 Run the following command to view the file system status:

ext*: **e2fsck -n** <disk-partition>

xfs: **xfs_repair -n** <disk-partition>

In this example, the ext4 file system is used. Therefore, run the following command:

e2fsck -n /dev/vdb1

Information similar to the following is displayed:

```
[root@ecs-test-0001 ~]# e2fsck -n /dev/vdb1
e2fsck 1.42.9 (28-Dec-2013)
Warning! /dev/vdb1 is mounted.
Warning: skipping journal recovery because doing a read-only filesystem check.
/dev/vdb1: clean, 11/6553600 files, 459544/26214144 blocks
```

If the file system status is **clean**, the file system is normal. Otherwise, rectify the faulty and then perform the capacity expansion.

----End

Method 2: Check Partition Style and File System Format Using parted

Step 1 Run the following command to view all the disks attached to the server:

lsblk

Information similar to the following is displayed:

```
[root@ecs-test-0001 ~]# lsblk
NAME MAJ:MIN RM SIZE RO TYPE MOUNTPOINT
vda   253:0   0  40G  0 disk
└─vda1 253:1   0  40G  0 part /
vdb   253:16  0 150G  0 disk
└─vdb1 253:17  0 100G  0 part /mnt/sdc
```

In this example, data disk **/dev/vdb** already has partition **/dev/vdb1** before capacity expansion, and the additional 50 GiB added has not been allocated yet. Therefore, **/dev/vdb** has 150 GiB, and **/dev/vdb1** has 100 GiB.

NOTE

If you run **lsblk** and find out that disk **/dev/vdb** has no partitions, format the disk by referring to [How Do I Extend the File System of an Unpartitioned Data Disk in Linux?](#) Otherwise, the additional space cannot be used after expansion.

Step 2 Run the following command and enter **p** to view the disk partition style:

parted <disk-name>

For example, run the following command to view **/dev/vdb**'s partition style:

parted /dev/vdb

Information similar to the following is displayed:

```
[root@ecs-test-0001 ~]# parted /dev/vdb
GNU Parted 3.1
Using /dev/vdb
Welcome to GNU Parted! Type 'help' to view a list of commands.
(parted) p
Error: The backup GPT table is not at the end of the disk, as it should be. This might mean that another
operating system believes the
disk is smaller. Fix, by moving the backup to the end (and removing the old backup)?
Fix/Ignore/Cancel? Fix
Warning: Not all of the space available to /dev/vdb appears to be used, you can fix the GPT to use all of
```

```
the space (an extra 104857600
blocks) or continue with the current setting?
```

```
Fix/Ignore? Fix
```

```
Model: Virtio Block Device (virtblk)
```

```
Disk /dev/vdb: 161GiB
```

```
Sector size (logical/physical): 512B/512B
```

```
Partition Table: gpt
```

```
Disk Flags:
```

Number	Start	End	Size	File system	Name	Flags
1	1049kB	107GiB	107GiB	ext4	test	

```
(parted)
```

Partition Table indicates the disk partition style. **Partition Table: msdos** means MBR, **Partition Table: gpt** means GPT, and **Partition Table: loop** means that the whole disk is partitioned.

- If the following error information is displayed, enter **Fix**.

```
Error: The backup GPT table is not at the end of the disk, as it should be. This might mean that
another operating system believes the
disk is smaller. Fix, by moving the backup to the end (and removing the old backup)?
```

The GPT partition table information is stored at the start of the disk. To reduce the risk of damage, a backup of the information is saved at the end of the disk. When you extend the disk, the end of the disk changes accordingly. In this case, enter **Fix** to move the backup file of the information to the end of the new disk.

- If the following warning information is displayed, enter **Fix**.

```
Warning: Not all of the space available to /dev/vdb appears to be used, you can fix the GPT to use all
of the space (an extra 104857600
blocks) or continue with the current setting?
Fix/Ignore? Fix
```

After you enter **Fix**, the system automatically sets the GPT partition style for the additional space.

Step 3 Enter **q** and press **Enter** to exit parted.

----End

6 Detachment

6.1 If I Detach a Disk, Will I Lose the Data on My Disk?

- Encrypted:
 - The custom key is disabled or scheduled for deletion.

The disk can still be used, but there is no guarantee for how long it will be usable. If the disk is detached, it will be impossible to re-attach it later. In this case, do not detach the disk without a working custom key.

The restoration method varies depending on the status of the key. For details, see [Managing Encrypted EVS Disks](#).
 - The custom key is available.

The disk can be detached and re-attached, and data on the disk will not be lost.

To ensure your data safety, you are advised to follow the instructions described in [Disk Detachment Process](#).
- Non-encrypted: Data on a disk will not be lost after the disk is detached, and the disk can be re-attached later if needed. To ensure your data safety, you are advised to follow the instructions described in [Disk Detachment Process](#).
- If you detach a disk that has an ongoing backup task, the task will fail.

Disk Detachment Process

- For disks not supporting online detachment:
 - a. Stop the server where the disk was attached.
 - b. After the server has stopped, detach the disk.
- For disks supporting online detachment:

Detach the disk from a running ECS. For details, see "Management" > "Detaching an EVS Disk from a Running ECS" in the *Elastic Cloud Server User Guide*.

6.2 Why Can't I Detach My Disk?

EVS disks can be used as system disks or data disks, but the way you detach each one is different.

NOTE

- In Linux, a system disk is typically mounted on **/dev/vda**. In Windows, a system disk is normally **Volume (C:)**.
- In Linux, a data disk is typically mounted on a mount point other than **/dev/vda**. In Windows, a data disk is normally a volume other than **Volume (C:)**.
- System disks: A system disk can only be detached offline. You must first stop the server that uses this system disk and then detach the disk.
- Data disks: A data disk can be detached regardless of whether it is offline or online.
 - Offline detachment: The server must be in the **Stopped** state. If it is not, stop the server and then detach the data disk.
 - Online detachment: Some OSs support online detachment. In this case, you do not need to stop the server before detaching the data disk. For more information, see [Detaching an EVS Disk from a Running ECS](#).

7 Deletion

7.1 How Can I Recover Data from a Disk That Was Accidentally Deleted?

Disk data was deleted: Check whether the disk has any snapshots or backups created.

- If there are, use a snapshot or backup to restore the disk data to the state when the snapshot or backup was created. For details, see [Rolling Back Disk Data from a Snapshot](#) or [Restoring from a Cloud Disk Backup](#).

NOTICE

If the disk was deleted after the last snapshot backup was created, that incremental data cannot be restored.

- If there are not, the disk data cannot be restored.

Disk was deleted: Check whether the recycle bin is enabled.

- If the recycle bin is enabled and the deleted disk is in the recycle bin, you can recover the disk. For details, see [Recovering Disks from the Recycle Bin](#).
- If the recycle bin is not enabled, the disk data cannot be restored.

7.2 Why Can't I Delete My Disk?

Check whether the following conditions are met:

- The disk status is **Available**, **Error**, **Expansion failed**, **Restoration failed**, or **Rollback failed**.
- The disk is not locked by any service.
- The shared disk has been detached from all its servers.
- The disk is not added to any replication pair in the Storage Disaster Recovery Service (SDRS). For any disk already added to a replication pair, you need to first [delete the replication pair](#) and then delete the disk.

- Yearly/Monthly system disks cannot be unsubscribed from separately. They must be unsubscribed from together with their servers.
- Non-shared, yearly/monthly data disks purchased together with or later added to a yearly/monthly server have the same expiration time as the server. They can be unsubscribed from together with the server or separately when their statuses are **In-use**, **Available**, or **Error**.
- Yearly/Monthly data disks purchased on the EVS console have different expiration times as the server. They can be unsubscribed from separately.

8 Capacity

8.1 What Is the Maximum Capacity Supported for the System and Data Disks?

The maximum capacity supported for a system disk is 1024 GiB.

The maximum capacity supported for a data disk is 32768 GiB.

8.2 What Should I Do If My Disk Starts to Run Out of Space?

If your disk space starts to fill up, you can:

1. Create a new disk and attach it to the server. For details, see [Purchasing an EVS Disk](#).
2. Expand the capacity of the existing disk. Both system disks and data disks can be expanded. An expansion operation includes two steps:
 - a. Expand the disk capacity on the console.
 - b. Log in to the server and extend the partition and file system.For details, see [Expanding EVS Disk Capacity](#).
3. Free up the space on the disk. For details, see [How Do I Clean Up My Disk Space on a Windows Server?](#)

Differences Between Expanding an EVS Disk and Creating an EVS Disk

The differences are as follows:

- Expanding an EVS disk is when you expand the capacity of an existing EVS disk. Some systems let you expand the capacity of EVS disks in use. In this case, services are not interrupted.
- If you create a new EVS disk and attach it to a server that already has an existing EVS disk, the new EVS disk and the original EVS disk are attached to the same server but independent from each other.

8.3 How Do I Clean Up My Disk Space on a Windows Server?

Scenarios

When the EVS disk space on a server is insufficient, the server running speed will be affected, which will further affect user experience. You can clean up the disk space using either of the following methods:

- **Cleaning Up Disk Space Using the System Built-in Cleanup Tool**

The following example uses a Windows Server 2016 server to illustrate how to clean up disk space on a server. In addition, you are advised to do the following to save disk space:

- Periodically compress and save the files that are not frequently used.
- Periodically use the disk cleanup tool to clean up disk space, delete unnecessary files, and clean up the recycle bin.
- Uninstall unnecessary programs to release disk space.

Cleaning Up Disk Space Using the System Built-in Cleanup Tool


Step 1 On the server desktop, click the start icon in the lower left corner.

The start menu is displayed.

Step 2 In the navigation pane on the left, choose **Windows Administrative Tools > Disk Cleanup**.


The **Disk Cleanup: Drive Selection** window is displayed.

Figure 8-1 Disk Cleanup: Drive Selection




Step 3 Select the target disk from the drop-down list. In this example, disk (C:) is selected.

The **Disk Cleanup** window is displayed, and the system automatically calculates the space that can be freed on disk (C:).

Figure 8-2 Disk Cleanup

Step 4 After the automatic calculation is complete, select the files to be deleted on the displayed window and click **OK**.

A confirmation dialog box is displayed.

Figure 8-3 Deletion confirmation

Step 5 Click **Delete Files** to clean up the disk space.

----End

Uninstalling Unnecessary Programs on Control Panel


Step 1 On the server desktop, click the start icon in the lower left corner.

The start menu is displayed.

Step 2 In the navigation pane on the left, choose **Windows System > Control Panel**.


The **All Control Panel Items** window is displayed.

Figure 8-4 All Control Panel Items



- Step 3** In the list, select **Programs and Features**.
The **Programs and Features** window is displayed.


Figure 8-5 Programs and Features



- Step 4** In the program list, right-click the program to be uninstalled and choose **Uninstall** from the shortcut menu.

A confirmation dialog box is displayed.

Figure 8-6 Uninstallation confirmation



Step 5 Click **Yes** to uninstall the program.

----End

8.4 What Can I Do If the Capacity of My Disk Reaches the Maximum But I Still Need More Space?

The capacity of a single disk can be expanded to up to 32 TiB. If this still fails to meet your needs, it is recommended that you [create RAID arrays with EVS disks](#) or [manage EVS disks using LVM](#).

8.5 What Should I Do If I Use fdisk to Initialize a Disk Larger Than 2 TiB and Then the Space in Excess of 2 TiB Cannot Be Displayed?

If your disk capacity is greater than 2 TiB, do not use fdisk to partition the disk. Or any space in excess of 2 TiB will be unable to show up after the disk is partitioned.

In this case, use parted to repartition the disk and choose the GPT partition style because MBR does not support disks over 2 TiB.

For details about how to initialize data disks, see [Introduction to Data Disk Initialization Scenarios and Partition Styles](#).

8.6 How Can I View the Available Capacity of My Disk?

You can view the available capacity of a disk on the ECS. The operations are as follows:

Step 1 Log in to the server.

For how to log in to an ECS, see [Logging In to an ECS](#).

For how to log in to a BMS, see [Logging In to a BMS](#).

Step 2 Query the disk capacity. Two methods are provided as follows:

- View the disk usage manually.

The details depend on the OS. This FAQ uses Windows Server 2008, Windows Server 2016, and Linux as examples to describe how to view the disk usage.

- [Viewing the Disk Usage in Linux](#)
 - [Viewing the Disk Usage in Windows Server 2008](#)
 - [Viewing the Disk Usage in Windows Server 2016](#)
 - Install the Agent to view the disk usage.
For details about how to install the Agent on an ECS, see [Installing the Agent on a Linux Server](#) in the *Cloud Eye User Guide*.
- End

Viewing the Disk Usage in Linux

In this section, CentOS 7.4 64bit is used as an example. The details depend on if you need to view the available space or not.

- To query the total capacity only, run **lsblk**.

Information similar to the following is displayed:

```
[root@ecs-test-0001 ~]# lsblk
NAME MAJ:MIN RM SIZE RO TYPE MOUNTPOINT
vda   253:0    0  40G  0 disk
├─vda1 253:1    0  40G  0 part /
vdb   253:16   0  40G  0 disk
├─vdb1 253:17   0  40G  0 part
```

In the command output, the server has two disks, **/dev/vda** and **/dev/vdb**. System disk **/dev/vda** has 40 GiB of capacity, as does data disk **/dev/vdb**.

- To query the total capacity and display the space available as well, run **df -TH**. Ensure that the disk has been attached and initialized before running this command.

Information similar to the following is displayed:

```
[root@ecs-0001 ~]# df -TH
Filesystem      Type      Size  Used Avail Use% Mounted on
/dev/vda1       ext4      43G   2.0G   39G   5% /
devtmpfs        devtmpfs  509M    0  509M   0% /dev
tmpfs           tmpfs     520M    0  520M   0% /dev/shm
tmpfs           tmpfs     520M   7.2M  513M   2% /run
tmpfs           tmpfs     520M    0  520M   0% /sys/fs/cgroup
tmpfs           tmpfs     104M    0  104M   0% /run/user/0
/dev/vdb1       ext4      43G   51M   40G   1% /mnt/sdc
```

In the command output, the server has two partitions, **/dev/vda1** and **/dev/vdb1**. Partition **/dev/vda1** is used to deploy the OS, and its total capacity, used capacity, and available capacity are 43 GiB, 2 GiB, and 39 GiB, respectively. Partition **/dev/vdb1**'s total capacity, used capacity, and available capacity are 43 GiB, 51 MiB, and 40 GiB, respectively.

Viewing the Disk Usage in Windows Server 2008

In this section, Windows Server 2008 R2 Enterprise 64bit is used as an example.


- Step 1** On the desktop of the server, right-click **Computer** and choose **Manage** from the shortcut menu.

The **Server Manager** window is displayed.

- Step 2** In the navigation tree, choose **Storage > Disk Management**.

The sizes and available spaces of the volumes on the current disk are displayed in the middle pane.

Figure 8-7 Disk Management page




----End

Viewing the Disk Usage in Windows Server 2016

In this section, Windows Server 2016 Standard 64bit is used as an example.

- Step 1** On the desktop of the server, click the start icon in the lower left corner.
The **Windows Server** window is displayed.
- Step 2** Click **Server Manager**.
The **Server Manager** window is displayed.


Figure 8-8 Server Manager page

Step 3 In the upper right corner, choose **Tools** > **Computer Management**.

Step 4 Choose **Storage** > **Disk Management**.

In the middle pane, you can view the sizes and available spaces of the volumes on the disk.

Figure 8-9 Disk list page



----End

Installing the Agent to View the Disk Usage

Some disk monitoring metrics require that the agent to be installed.

For details about how to install the Agent on an ECS, see [Installing the Agent on a Linux Server](#) in the *Cloud Eye User Guide*.

Table 8-1 Disk metrics

Metric	Parameter	Description	Value Range	Unit	Conversion Rule	Monitored Object & Dimension	Monitoring Period (Raw Data)
disk_free	(Agent) Available Disk Space	Free space on the disks - Linux: Run the df -h command to check the value in the Avail column. The path of the mount point prefix cannot exceed 64 characters. It must start with a letter, and contain only digits, letters, hyphens (-), periods (.), and swung dashes (~). - Windows: Use the WMI interface to call GetDiskFreeSpaceExW API to obtain disk space data. The path of the mount point prefix cannot exceed 64 characters. It must start with a letter, and contain only digits, letters, hyphens (-), periods (.), and swung dashes (~).	≥0	GB	N/A	ECS - Mount point	1 minute

Metric	Parameter	Description	Value Range	Unit	Conversion Rule	Monitored Object & Dimension	Monitoring Period (Raw Data)
disk_total	(Agent) Disk Storage Capacity	Total space on the disks, including used and free - Linux: Run the df -h command to check the value in the Size column. The path of the mount point prefix cannot exceed 64 characters. It must start with a letter, and contain only digits, letters, hyphens (-), periods (.), and swung dashes (~). - Windows: Use the WMI interface to call GetDiskFreeSpaceExW API to obtain disk space data. The path of the mount point prefix cannot exceed 64 characters. It must start with a letter, and contain only digits, letters, hyphens (-), periods (.), and swung dashes (~).	≥0	GB	N/A	ECS - Mount point	1 minute

Metric	Parameter	Description	Value Range	Unit	Conversion Rule	Monitored Object & Dimension	Monitoring Period (Raw Data)
disk_used	(Agent) Used Disk Space	Used space on the disks - Linux: Run the df -h command to check the value in the Used column. The path of the mount point prefix cannot exceed 64 characters. It must start with a letter, and contain only digits, letters, hyphens (-), periods (.), and swung dashes (~). - Windows: Use the WMI interface to call GetDiskFreeSpaceExW API to obtain disk space data. The path of the mount point prefix cannot exceed 64 characters. It must start with a letter, and contain only digits, letters, hyphens (-), periods (.), and swung dashes (~).	≥0	GB	N/A	ECS - Mount point	1 minute

Metric	Parameter	Description	Value Range	Unit	Conversion Rule	Monitored Object & Dimension	Monitoring Period (Raw Data)
disk_usedPercent	(Agent) Disk Usage	Percentage of total disk space that is used, which is calculated as follows: Disk Usage = Used Disk Space/Disk Storage Capacity - Linux: It is calculated as follows: Used/Size. The path of the mount point prefix cannot exceed 64 characters. It must start with a letter, and contain only digits, letters, hyphens (-), periods (.), and swung dashes (~). - Windows: Use the WMI interface to call GetDiskFreeSpace ExW API to obtain disk space data. The path of the mount point prefix cannot exceed 64 characters. It must start with a letter, and contain only digits, letters, hyphens (-), periods (.), and swung dashes (~).	0-100	%	N/A	ECS - Mount point	1 minute

8.7 How Can I Monitor My Disk Usages?

Some disk monitoring metrics require that the agent to be installed.

For details about how to install the Agent on an ECS, see [Installing the Agent on a Linux Server](#) in the *Cloud Eye User Guide*.

Table 8-2 Disk metrics

Metric	Parameter	Description	Value Range	Unit	Conversion Rule	Monitored Object & Dimension	Monitoring Period (Raw Data)
disk_free	(Agent) Available Disk Space	Free space on the disks - Linux: Run the df -h command to check the value in the Avail column. The path of the mount point prefix cannot exceed 64 characters. It must start with a letter, and contain only digits, letters, hyphens (-), periods (.), and swung dashes (~). - Windows: Use the WMI interface to call GetDiskFreeSpaceExW API to obtain disk space data. The path of the mount point prefix cannot exceed 64 characters. It must start with a letter, and contain only digits, letters, hyphens (-), periods (.), and swung dashes (~).	≥0	GB	N/A	ECS - Mount point	1 minute

Metric	Parameter	Description	Value Range	Unit	Conversion Rule	Monitored Object & Dimension	Monitoring Period (Raw Data)
disk_total	(Agent) Disk Storage Capacity	Total space on the disks, including used and free - Linux: Run the df -h command to check the value in the Size column. The path of the mount point prefix cannot exceed 64 characters. It must start with a letter, and contain only digits, letters, hyphens (-), periods (.), and swung dashes (~). - Windows: Use the WMI interface to call GetDiskFreeSpaceExW API to obtain disk space data. The path of the mount point prefix cannot exceed 64 characters. It must start with a letter, and contain only digits, letters, hyphens (-), periods (.), and swung dashes (~).	≥0	GB	N/A	ECS - Mount point	1 minute

Metric	Parameter	Description	Value Range	Unit	Conversion Rule	Monitored Object & Dimension	Monitoring Period (Raw Data)
disk_used	(Agent) Used Disk Space	Used space on the disks - Linux: Run the df -h command to check the value in the Used column. The path of the mount point prefix cannot exceed 64 characters. It must start with a letter, and contain only digits, letters, hyphens (-), periods (.), and swung dashes (~). - Windows: Use the WMI interface to call <code>GetDiskFreeSpaceExW</code> API to obtain disk space data. The path of the mount point prefix cannot exceed 64 characters. It must start with a letter, and contain only digits, letters, hyphens (-), periods (.), and swung dashes (~).	≥0	GB	N/A	ECS - Mount point	1 minute

Metric	Parameter	Description	Value Range	Unit	Conversion Rule	Monitored Object & Dimension	Monitoring Period (Raw Data)
disk_usedPercent	(Agent) Disk Usage	Percentage of total disk space that is used, which is calculated as follows: Disk Usage = Used Disk Space/Disk Storage Capacity - Linux: It is calculated as follows: Used/Size. The path of the mount point prefix cannot exceed 64 characters. It must start with a letter, and contain only digits, letters, hyphens (-), periods (.), and swung dashes (~). - Windows: Use the WMI interface to call GetDiskFreeSpace ExW API to obtain disk space data. The path of the mount point prefix cannot exceed 64 characters. It must start with a letter, and contain only digits, letters, hyphens (-), periods (.), and swung dashes (~).	0-100	%	N/A	ECS - Mount point	1 minute

8.8 Can I Transfer the Data Disk Capacity to a System Disk?

Sorry, you cannot.

Currently, the capacity of an EVS disk cannot be transferred to another disk. Multiple EVS disks cannot be combined into a single, larger disk, either.

Common Scenarios

1. You want to expand the system disk capacity, but purchased a new data disk.
2. You want to expand the system disk capacity, but expanded the data disk capacity.

Recommended Solution

- If you do not need the data on the data disk, you can just delete or unsubscribe from the data disk, and then [expand the system disk](#).
- If you need the data on the data disk, you can purchase a small-capacity data disk, copy data from the original data disk to the new data disk, and then expand the system disk capacity.
 - a. Back up the data disk using the CBR service or by creating a snapshot.
For details about backups, see [Managing EVS Backups](#). For details about snapshots, see [Creating a Snapshot](#).
 - b. Buy a new data disk with the desired capacity and attach it to the server. After initializing the disk, copy the data from the original data disk to the new data disk.
 - c. Confirm that the services on the new data disk are available. Then, delete or unsubscribe from the original data disk, and delete the created backup.
 - d. Expand the system disk capacity by referring to [Expanding the EVS Disk Capacity](#).

8.9 Why the Space of My New Disk Is Full After I Uploaded Only 500 MB of Files to the Disk?

Troubleshoot this issue by performing the following steps:

1. Check whether the disk partition usage is 100% or almost 100%.
`df -h`

Figure 8-10 Checking the partition usage


```
[root@ecs-a058 ~]# df -h
Filesystem      Size  Used Avail Use% Mounted on
devtmpfs        7.8G   0  7.8G   0% /dev
tmpfs           7.8G  20K  7.8G   1% /dev/shm
tmpfs           7.8G  8.7M  7.8G   1% /run
tmpfs           7.8G   0  7.8G   0% /sys/fs/cgroup
/dev/vda1       99G   99G   0 100% /
tmpfs           1.6G   0  1.6G   0% /run/user/0
```

In this example, the `/dev/vda1` partition usage is 100%.

2. Check the disk space usage.

```
df -i
```

Figure 8-11 Checking the disk space usage




Filesystem	Inodes	IUsed	IFree	IUse%	Mounted on
devtmpfs	2030569	369	2030200	1%	/dev
tmpfs	2033158	2	2033156	1%	/dev/shm
tmpfs	2033158	507	2032651	1%	/run
tmpfs	2033158	16	2033142	1%	/sys/fs/cgroup
/dev/vda1	6553600	139249	6414351	3%	/
tmpfs	2033158	1	2033157	1%	/run/user/0

In this example, the disk space usage is low.

3. Check the deleted process files in the system.

```
ls -l | grep deleted
```

Figure 8-12 Checking the deleted process files in the system



Permissions	Size	Owner	Group	File Type	File Path
-rwxr-xr-x	2687	root	txt	REG	/usr/sbin/agetty:5ea3f3
-rwxr-xr-x	8019	mysql	5u	REG	/tmp/ibTwxfsx (deleted)
-rwxr-xr-x	8019	mysql	6u	REG	/tmp/ib0KEqPb (deleted)
-rwxr-xr-x	8019	mysql	7u	REG	/tmp/ibX0VBcQ (deleted)
-rwxr-xr-x	8019	mysql	8u	REG	/tmp/ib73Mfc9 (deleted)
-rwxr-xr-x	8019	mysql	14u	REG	/tmp/ib00UESN (deleted)
-rwxr-xr-x	8019	8020	mysql	5u	/tmp/ibTwxfsx (deleted)
-rwxr-xr-x	8019	8020	mysql	6u	/tmp/ib0KEqPb (deleted)
-rwxr-xr-x	8019	8020	mysql	7u	/tmp/ibX0VBcQ (deleted)
-rwxr-xr-x	8019	8020	mysql	8u	/tmp/ib73Mfc9 (deleted)
-rwxr-xr-x	8019	8020	mysql	14u	/tmp/ib00UESN (deleted)
-rwxr-xr-x	8019	8021	mysql	5u	/tmp/ibTwxfsx (deleted)
-rwxr-xr-x	8019	8021	mysql	6u	/tmp/ib0KEqPb (deleted)
-rwxr-xr-x	8019	8021	mysql	7u	/tmp/ibX0VBcQ (deleted)
-rwxr-xr-x	8019	8021	mysql	8u	/tmp/ib73Mfc9 (deleted)
-rwxr-xr-x	8019	8021	mysql	14u	/tmp/ib00UESN (deleted)
-rwxr-xr-x	8019	8022	mysql	5u	/tmp/ibTwxfsx (deleted)
-rwxr-xr-x	8019	8022	mysql	6u	/tmp/ib0KEqPb (deleted)
-rwxr-xr-x	8019	8022	mysql	7u	/tmp/ibX0VBcQ (deleted)
-rwxr-xr-x	8019	8022	mysql	8u	/tmp/ib73Mfc9 (deleted)
-rwxr-xr-x	8019	8022	mysql	14u	/tmp/ib00UESN (deleted)
-rwxr-xr-x	8019	8023	mysql	5u	/tmp/ibTwxfsx (deleted)
-rwxr-xr-x	8019	8023	mysql	6u	/tmp/ib0KEqPb (deleted)
-rwxr-xr-x	8019	8023	mysql	7u	/tmp/ibX0VBcQ (deleted)
-rwxr-xr-x	8019	8023	mysql	8u	/tmp/ib73Mfc9 (deleted)
-rwxr-xr-x	8019	8023	mysql	14u	/tmp/ib00UESN (deleted)
-rwxr-xr-x	8019	8024	mysql	5u	/tmp/ibTwxfsx (deleted)
-rwxr-xr-x	8019	8024	mysql	6u	/tmp/ib0KEqPb (deleted)
-rwxr-xr-x	8019	8024	mysql	7u	/tmp/ibX0VBcQ (deleted)
-rwxr-xr-x	8019	8024	mysql	8u	/tmp/ib73Mfc9 (deleted)
-rwxr-xr-x	8019	8024	mysql	14u	/tmp/ib00UESN (deleted)
-rwxr-xr-x	8019	8025	mysql	5u	/tmp/ibTwxfsx (deleted)
-rwxr-xr-x	8019	8025	mysql	6u	/tmp/ib0KEqPb (deleted)
-rwxr-xr-x	8019	8025	mysql	7u	/tmp/ibX0VBcQ (deleted)
-rwxr-xr-x	8019	8025	mysql	8u	/tmp/ib73Mfc9 (deleted)
-rwxr-xr-x	8019	8025	mysql	14u	/tmp/ib00UESN (deleted)
-rwxr-xr-x	8019	8026	mysql	5u	/tmp/ibTwxfsx (deleted)
-rwxr-xr-x	8019	8026	mysql	6u	/tmp/ib0KEqPb (deleted)
-rwxr-xr-x	8019	8026	mysql	7u	/tmp/ibX0VBcQ (deleted)
-rwxr-xr-x	8019	8026	mysql	8u	/tmp/ib73Mfc9 (deleted)
-rwxr-xr-x	8019	8026	mysql	14u	/tmp/ib00UESN (deleted)

Roughly calculate the total size of the deleted files based on the returned command output. If it is almost the same as the used space of the disk, the disk space may be used up by the deleted processes that have not been released.

4. Go to the location of a deleted file to check whether the file is still there.

```
ll /tmp/
```

Note that variable `/tmp/` in the command indicates the path of the deleted file.

5. If the file is not there, run the following command to terminate the process, or restart the server to release the used space.

```
kill -9 PID
```

Note that variable *PID* in the command indicates the process ID.

6. Check that the process is terminated.

```
lsuf | grep deleted
```

7. Check that the disk partition usage is no longer 100%.

```
df -h
```

9 Snapshot

9.1 What Are the Typical Causes of a Snapshot Creation Failure?

A snapshot creation will fail if its source disk is in an intermediate state, such as **Attaching** and **Expanding**, or an abnormal state, such as **Error** and **Restoration failed**.

Ensure that a disk is in the **In-use** or **Available** state before creating a snapshot.

9.2 Does EVS Support Automatic Snapshot Creation?

No, but you can develop a program to periodically create snapshots through APIs. Alternatively, you may use the CBR service and enable auto backup to create backups periodically. For details, see [Creating a Backup Policy](#).

9.3 Can I Create Snapshots for Multiple Disks at a Time?

No. Snapshots cannot be created for multiple disks at the same time. You must create snapshots for disks one by one.

9.4 How Is a Snapshot Created for My Disk?

There are two types of snapshots: manual snapshots you create on-demand and automatic snapshots created by the system.

- Manual snapshots: You may manually create snapshots to rapidly save the disk data at specific points of time. This feature is now in open beta testing and is free for trial use. For details about how to create snapshots, see [Creating a Snapshot \(OBT\)](#).
- Automatic snapshots: During the creation of a cloud server backup, or a disk backup with the CBR service, the system automatically creates a snapshot and

saves the latest snapshot for each disk. If a disk already has a backup, after another backup, the old snapshot will be deleted and the latest one will be retained. This snapshot is free of charge. You can view the snapshot details only but cannot perform any operations on it.

9.5 Why Can't I Roll Back My Disk Data from a Snapshot?

Possible causes are as follows:

- Snapshot data can only be rolled back when the status of the snapshot's source disk is **Available** or **Rollback failed**. If the snapshot's source disk is **In-use**, detach the disk and then use the snapshot to roll back disk data. After the rollback succeeds, re-attach the disk.
- Snapshot data can only be rolled back to source EVS disks. Rollback to a different disk is not possible.
- If the snapshot is being created, it cannot be used to roll back disk data.
- A snapshot whose name starts with **autobk_snapshot_vbs_**, **manualbk_snapshot_vbs_**, **autobk_snapshot_csbs_**, or **manualbk_snapshot_csbs_** is automatically generated during backup. Such a snapshot can only be viewed. It cannot be used to roll back the disk data.

9.6 Can I Roll Back Data from a Snapshot After Reinstalling the OS or Formatting a Disk?

- If you have reinstalled or changed the server OS: Legacy snapshots of the system disk will be deleted. Standard snapshots will not be deleted but Instant Snapshot Restore will be disabled automatically. Snapshots of the data disks can be used as usual.
- If you have formatted a disk, snapshots can still be used to roll back the disk data.

9.7 How Is the Snapshot Size Calculated?

The first snapshot is a full snapshot, which backs up all data (data blocks) on the EVS disk at the time of the snapshot. Subsequent snapshots are incremental snapshots, which back up only changed data blocks since the last snapshot.

9.8 Do Snapshots Take Space on the Disk?

No.

Creating legacy snapshots establishes relationships between snapshots and the disk data. Snapshots are stored on the physical disks that provide storage resources for EVS disks and do not use the EVS disk space.

Standard snapshots are stored in OBS, instead of on disks. They can be used to restore data when the disk is damaged.

For more information about EVS snapshot principles, see [Snapshot Principles](#).

9.9 Can I Perform Multiple Rollback Operations for a Snapshot?

Yes. You can use a snapshot to roll back data to the source disk multiple times as needed.

9.10 Can I Replicate Snapshots to Other Regions or Accounts?

No. Snapshots cannot be replicated to other regions or accounts.

9.11 Why Can't I Find My Snapshot?

Possible causes are:

- You have manually deleted the snapshot.
- You have deleted the snapshot's source disk. Then, all the legacy snapshots created for this disk will be deleted automatically.
- You have reinstalled or changed the server OS. System disk snapshots will be automatically deleted after a server OS has been reinstalled or changed.

9.12 Can I Use a Snapshot to Create a Disk and Roll Back Disk Data at Almost the Same Time?

The following two scenarios are supported:

- You can first use a snapshot to create a disk and then use the snapshot to roll back data of its source disk.
- You can first use a snapshot to roll back data of its source disk and then use the snapshot to create a disk.

10 Performance

10.1 How Do I Test My Disk Performance?

Precautions

In the disk performance test, if the first sector number is not 4-KiB aligned, the disk performance will be greatly affected. Ensure that the first sector number is 4-KiB aligned before you start the test.

NOTE

To test the performance of a shared disk, the following requirements must be met:

- The shared disk must be attached to multiple servers (ECSs or BMSs).
- If the shared disk is attached to multiple ECSs, these ECSs must belong to the same anti-affinity ECS group.
If these ECSs fail to meet the anti-affinity requirement, the shared disk cannot reach the optimal performance.

The testing process for Windows and Linux is different.

- [Windows](#)
- [Linux](#)

If the test results do not meet your expectation, see [Why Does My Disk Performance Test Using Fio Have Incorrect Results?](#)

Windows

The way you test disk performance depends on the server OS. This section uses Windows Server 2019 Standard 64-bit as an example. For other Windows OSs, see the corresponding OS documentations.

Install the performance measurement tool Iometer before the test. You can obtain the tool at <http://www.iometer.org/>.

Step 1 Log in to the server.

Step 2 Press **win+R** to open the **Run** window. Enter **msinfo32** and click **OK**.

The system information window is displayed.

Step 3 Choose **components > storage > disks**. In the right pane, view the partition offset.

- If 4096 can be divided by the parameter value, the partition is 4-KiB aligned. Go to [Step 4](#).
- If 4096 cannot be divided by the parameter value, the partition is not 4-KiB aligned. Ensure 4-KiB alignment for the partition before continuing the test.

NOTICE


If you delete the partition and select another first sector number for 4-KiB alignment, you will lose all the data on that partition.

Step 4 Use iometer to test the disk performance. For details, see the iometer product documentation.

When the disk IOPS and throughput are tested, the parameter settings for iometer and fio are the same. For details, see [Table 10-1](#).


The following example uses iometer to test the disk performance.

1. Set the workflow.




2. Set the test run time.


In this example, the test run time is set to 10 minutes, with 60 seconds ramp up time. Disk performance is tested after the writes are stable.



3. Set the data block size and read/write policy. In this example, the disk size is set to 64 KiB, the policy is 100% sequential write.



4. View the test results.



----End

Linux

If you use an old version Linux OS, for example CentOS 6.5, and run **fdisk** to create partitions, the default first sector number will not be 4-KiB aligned, which will greatly affect the test performance. For this reason, if such an OS is used, you are advised to select a new first sector number, one that is 4-KiB aligned, when creating partitions.

The way you test disk performance depends on the server OS. This section uses CentOS 7.2 64-bit as an example. For other Linux OSs, see the corresponding OS documentations.

- Step 1** Log in to the server and switch to user **root**.
- Step 2** Install the performance test tool fio.
yum install fio
- Step 3** Before you start the test, run the following command to check whether the first sector number is 4-KiB aligned:

fdisk -lu

Information similar to the following is displayed:
[root@ecs-centos sdc]# fdisk -lu

Disk /dev/xvda: 10.7 GiB, 10737418240 bytes, 20971520 sectors
Units = sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disk label type: dos
Disk identifier: 0x7db77aa5

```
Device Boot      Start         End      Blocks   Id  System
/dev/xvda1 *        2048       20968919    10483436    83  Linux

Disk /dev/xvdb: 10.7 GiB, 10737418240 bytes, 20971520 sectors
Units = sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes

Disk /dev/xvdc: 53.7 GiB, 53687091200 bytes, 104857600 sectors
Units = sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disk label type: dos
Disk identifier: 0x3cf3265c

Device Boot      Start         End      Blocks   Id  System
/dev/xvdc1        2048       41943039    20970496    83  Linux
```

- If 8 can be divided by the first sector number, the number is 4-KiB aligned. Go to [Step 4](#).
- If 8 cannot be divided by the first sector number, the number is not 4-KiB aligned. Delete the partition and select a 4-KiB aligned first sector number for the new partition before continuing the test.

NOTICE

If you delete the partition and select another first sector number for 4-KiB alignment, you will lose all the data on that partition.

Step 4 Run the following commands and use fio to test the disk performance:

- To test random write IOPS, run the following command: **fio -direct=1 -iodepth=128 -rw=randwrite -ioengine=libaio -bs=4k -size=10G -numjobs=1 -runtime=600 -group_reporting -filename=/opt/fiotest/fiotest.txt -name=Rand_Write_IOPS_Test**
- To test random read IOPS, run the following command: **fio -direct=1 -iodepth=128 -rw=randread -ioengine=libaio -bs=4k -size=10G -numjobs=1 -runtime=600 -group_reporting -filename=/opt/fiotest/fiotest.txt -name=Rand_Read_IOPS_Test**
- To test write throughput, run the following command: **fio -direct=1 -iodepth=32 -rw=write -ioengine=libaio -bs=1024k -size=10G -numjobs=1 -runtime=600 -group_reporting -filename=/opt/fiotest/fiotest.txt -name=Write_BandWidth_Test**
- To test read throughput, run the following command: **fio -direct=1 -iodepth=32 -rw=read -ioengine=libaio -bs=1024k -size=10G -numjobs=1 -runtime=600 -group_reporting -filename=/opt/fiotest/fiotest.txt -name=Read_BandWidth_Test**
- To test single-queue, random read latency, run the following command: **fio -direct=1 -iodepth=1 -rw=randread -ioengine=libaio -bs=4k -size=10G -numjobs=1 -runtime=60 -group_reporting -filename=/opt/fiotest/fiotest.txt -name=Rand_Read_LATE_Test**

NOTICE

- When using fio to perform a raw disk performance test, ensure that no partitions and file systems have been created on the disk and there is no data stored on the disk. Or, the raw disk test will damage the file system, and data on the disk will become read-only. In this case, your only option will be to delete the disk and buy a new one to continue the test.
- Do not perform the test on a disk with service data on it. If such test is a must, you are advised to perform the test as follows:
 - Back up the disk data before the test as you may damage the data on the disk.
 - Specify a file, for example **-filename=/opt/fiotest/fiotest.txt**, to test the performance of the file system.

Table 10-1 lists the fio test parameters.

Table 10-1 Parameter description

Parameter	Description
direct	Defines whether direct I/O is used. - Set to 0: buffered I/O is used. - Set to 1: direct I/O is used.
iodepth	Defines the I/O queue depth. This queue depth refers to the queue depth of each thread regardless of whether a single or multiple threads are used in the test. Total concurrent I/Os of fio = <code>iodepth</code> x <code>numjobs</code> Examples: - If there is a single thread and -iodepth=32, the I/O queue depth of this thread is 32 and the total concurrent I/Os of fio is 32 (32 x 1). - If there are three threads and -iodepth=32, the I/O queue depth of each thread is 32 and the total concurrent I/Os of fio is 96 (32 x 3).
rw	Defines the test read/write policy. - randread: random read - randwrite: random write - read: sequential read - write: sequential write - randrw: mixed random read/write

Parameter	Description
ioengine	Defines how fio delivers the I/O request (synchronously or asynchronously). – Synchronous I/O: Only one I/O request is delivered at a time, and the response is returned after the kernel has processed the request. That said, the single-thread I/O queue depth is always less than 1, and multi-thread concurrent processing can be used to handle such issues. Normally, 16 to 32 concurrent working threads fully occupy the I/O queue depth. – Asynchronous I/O: Multiple I/O requests are delivered using libaio at a time. Wait for the process to complete and reduce the interaction times to improve efficiency.
bs	Defines the I/O block size. The unit can be KiB, Kb, MiB, and Mb, and the default value is 4 KiB.
size	Defines the amount of data processed by the test I/Os. If parameters, such as runtime, are not specified, the test ends when fio has processed all the specified data amount. The value can be a number with a unit or percentage. A number with a unit indicates the read/write data amount, for example size=10G, indicating a 10-GiB read/write data amount. A percentage indicates the ratio of read/write data amount to the total size of files, for example size=20%, indicating the read/write data amount takes 20% of the total file space.
numjobs	Defines the number of concurrent threads.
runtime	Defines the test time. If this parameter is not specified, the test ends until the specified data amount is processed by the block size defined using parameter size.
group_reporting	Defines the test result display mode. The parameter value displays the statistics on a single thread instead of that on all jobs.
filename	Defines the name of the test file or device. – If a file is specified, the performance of the file system is tested. Example: -filename=/opt/fiotest/fiotest.txt – If a device name is specified, the performance of the raw disk is tested. Example: -filename=/dev/vdb NOTICE If the test is performed on a disk already has partitions and file systems created as well as data on it, user parameter filename to specify a file so that the original file system is not damaged and the data is not overwritten.
name	Defines the test task name.

----End

10.2 Why Does My Disk Performance Test Using Fio Have Incorrect Results?

Symptom

You have followed the test performance method, but the test results do not meet expectations.

Troubleshooting

During a disk performance test, the disk and stress test conditions play an important role.

Possible causes are listed here in order of their probability.

If the fault persists after you have ruled out one cause, move on to the next one in the list.

NOTICE

Some operations may result in data loss. It is recommended that you use raw disks for performance test.

Figure 10-1 Troubleshooting




Table 10-2 Troubleshooting

Possible Cause	Solution
The partition's first sector number is not 4-KiB aligned.	Go to Check Whether Partition's First Sector Number Is 4-KiB Aligned . Delete the partition and select a 4-KiB aligned first sector number for the new partition.
The disk used in testing was not a raw disk.	Purchase an empty disk and attach it to a server for testing.
Stress test conditions were not properly set.	Configure multi-core processing and arrange queues properly to maximize the concurrent performance.
An inappropriate data block size was used.	Set a suitable data block size. - When testing the disk IOPS, set the data block size to a small value, for example, 4 KiB. - When testing the disk throughput, set the data block size to a large value, for example, 1024 KiB.

Check Whether Partition's First Sector Number Is 4-KiB Aligned

Step 1 Log in to the server and switch to user **root**.

Step 2 Before you start the test, run the following command to check whether the first sector number is 4-KiB aligned:

fdisk -lu

Information similar to the following is displayed:

```
[root@ecs-centos sdc]# fdisk -lu
```

```
Disk /dev/xvda: 10.7 GiB, 10737418240 bytes, 20971520 sectors
Units = sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disk label type: dos
Disk identifier: 0x7db77aa5
```

```
Device Boot      Start         End      Blocks   Id  System
/dev/xvda1 *        2048     20968919     10483436   83  Linux
```

```
Disk /dev/xvdb: 10.7 GiB, 10737418240 bytes, 20971520 sectors
Units = sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
```

```
Disk /dev/xvdc: 53.7 GiB, 53687091200 bytes, 104857600 sectors
Units = sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disk label type: dos
Disk identifier: 0x3cf3265c
```

```
Device Boot      Start         End      Blocks   Id  System
/dev/xvdc1        2048     41943039     20970496   83  Linux
```

- If 8 can be divided by the first sector number, the number is 4-KiB aligned.
- If 8 cannot be divided by the first sector number, the number is not 4-KiB aligned. Delete the partition and select a 4-KiB aligned first sector number for the new partition before continuing the test.

NOTICE

If you delete the partition and select another first sector number for 4-KiB alignment, you will lose all the data on that partition.

-----End

Submitting a Service Ticket

If the problem persists, [submit a service ticket](#).

10.3 How Can I Handle a Slowdown in Disk Read/Write Speed or Increased I/Os?

Symptom

If you are aware of a service slowdown, depending on if you are examining a Windows or Linux server, you can take the following actions:

- Windows: Open **Task Manager** and view the average response time.
- Linux: Run **iostat -dx** to view the I/O performance.

If the disk read/write speed is slowed down, disk I/O increases, or the await time increases, the disk is likely to encounter a performance bottleneck.


Solution

Method 1: Change to a disk type with a higher specification. For details, see [Changing the EVS Disk Type](#).

Method 2: Create a new disk from a disk backup to retain the disk data. The procedure is as follows:

1. Create a backup for the disk.

Figure 10-2 Create Backup



2. Create a new disk from this backup. During the creation, select a new disk type and configure advanced settings (sharing, SCSI, and encryption) based on your service requirements.

Figure 10-3 Create from backup

The screenshot shows the 'Buy Disk' interface. At the top, there's a 'Region' dropdown set to 'CN North-Beijing4'. Below it, 'AZ' options are shown: 'AZ1' (selected), 'AZ2 (1)', 'AZ3', and 'AZ7'. A note states: 'No server is available in the current AZ. Select the AZ where your server resides. The AZ cannot be changed after the disk is created.' The 'Attach To Server (Optional)' section has a 'Select Server' button. The 'Billing Mode' section has 'Yearly/Monthly' and 'Pay-per-use' (selected) buttons. The 'Data Source (Optional)' section has a 'Create from' dropdown menu with 'Backup' (highlighted with a red box), 'Snapshot', and 'Image' options. The 'Disk Specifications' section shows 'Ultra SSD' and '10 GiB'. The 'Automatic Backup' section has 'Do not use', 'Use existing', and 'Buy new' buttons. At the bottom, there are links for 'Share', 'SCSI', 'Encryption', and 'Tag'.

10.4 How Can I Improve My Disk Performance?

You can use the following methods to improve your disk performance:

- [RAID Array Creation with EVS Disks](#)
- [Using LVM to Manage EVS Disks](#)

10.5 Why My Disk's Read IOPS Can't Reach the Theoretical Maximum IOPS When the Disk I/O Usage Is Almost 100%?

Symptom

A 500 GiB ultra-high I/O disk had an I/O usage of 99.94%, but it only had 12,000 IOPS.

Description

- **100% disk I/O usage does not mean that the disk IOPS reaches the maximum.**

Disk I/O usage calculates the read or write operations performed by a disk in a measurement period. It describes how busy a disk is, not the disk I/O performance.

EVS disks can process I/O requests concurrently, so 100% disk I/O usage does not mean that the disk encounters the performance bottleneck. For example,

an EVS disk takes 0.1 second to process an I/O request and can process 10 I/O requests concurrently. If 10 I/O requests are submitted serially, the disk takes 1 second to process all I/O requests. In this 1-second measurement period, the disk I/O usage reaches 100%. However, if 10 I/O requests are submitted concurrently, the disk takes just 0.1 second to process all the requests. This way, the disk I/O usage in a 1-second measurement period is only 10%. This means that a disk can still process I/O requests even if its I/O usage reaches 100%.

- **Why does the disk not reach the theoretical maximum IOPS?**

The actual maximum IOPS that a disk can reach is calculated as follows: $\text{Disk IOPS} = \text{Min. (Max. IOPS, Min. IOPS} + \text{IOPS per GiB} \times \text{Disk size})$. For a 500 GiB ultra-high I/O disk, its IOPS is calculated as follows: $\text{Disk IOPS} = \text{Min. (50,000, 1,800} + 50 \times 500) = 26,800$

The disk read IOPS is the number of read operations performed by the disk per second. IOPS is also affected by latency. In a single-queue access scenario with 4 KiB data blocks, the access latency of an ultra-high I/O disk is 1 ms, which means the disk can process 1,000 requests (IOPS) in a second. 12,000 IOPS indicates that the queue depth is 12. To reach the theoretical maximum IOPS (26,800), the queue depth should reach 26.

11 Sharing

11.1 Do I Have to Deploy a Cluster to Use Shared Disks?

Yes.

If you simply attach a shared disk to multiple servers, files cannot be shared among them. Because there are no mutually agreed data read/write rules among servers, read and write operations from them may interfere with each other, or unpredictable errors may occur.

Shared EVS disks do not have cluster management capabilities. You need to build a clustered system for data sharing, such as Windows MSCS, Veritas VCS, and Veritas CFS clusters.

11.2 How Many Servers Can I Attach a Shared Disk to?

A shared disk can be attached to up to 16 servers.

11.3 How Can I Attach a Shared Disk to Multiple Servers?

A shared disk can be attached to multiple servers on the console. You can choose to attach it to servers one by one or in a batch.

For details, see [Attaching a Shared Disk](#).

11.4 Can a Shared Disk Be Attached to Servers That Belong to Different Accounts?

No. A shared disk can only be attached to servers that belong to the same account and are in the same AZ.

11.5 Can I Attach a Shared Disk to Servers Running Different OSs?

- It is recommended that you do not attach a shared disk to both Linux and Windows servers.
- If you attach a shared disk to servers running different versions of the same OS type, for example CentOS 6 and CentOS 7 servers, you can use the shared disk normally.

12 Backup

12.1 Do I Need to Stop the Server Before Performing a Disk Backup?

No. You can back up disks when the server is in use. When a server is running, data is written into disks on the server, and some newly generated data is cached in the server memory. During a backup task, data in the memory will not be automatically written into disks, so the disk data and their backups may be inconsistent.

To ensure data integrity, you are advised to perform the backup during off-peak hours when no data is written to the disks. For applications that require strong consistency, such as databases and email systems, you are advised to enable application-consistent backup.

12.2 Can I Back Up and Restore My EVS Disk to a Different Region?

In-use EVS disks (attached to ECSs) support cross-region backup and restoration. CBR cloud server backup supports cross-region replication. You can back up such disks by backing up their ECSs. Then, replicate the server backups to your desired region and use the replicated backups to create images and provision servers.

EVS disks that are not attached to any ECS cannot be backed up or restored across regions.

12.3 How Do I Check the Backup Data of My Disk?

1. Create a new disk from a disk backup. For details, see [Creating a Disk from a Cloud Disk Backup](#).
2. Attach the disk to a server. For details, see [Attaching a Non-Shared Disk](#) or [Attaching a Shared Disk](#).
3. Log in to the server to check the disk data.